



# Mac OS X Server Print Server Administration

For Version 10.6 Snow Leopard

© 2009 Apple Inc. All rights reserved.

The owner or authorized user of a valid copy of Mac OS X Server software may reproduce this publication for the purpose of learning to use such software. No part of this publication may be reproduced or transmitted for commercial purposes, such as selling copies of this publication or for providing paid-for support services.

Every effort has been made to ensure that the information in this manual is accurate. Apple Inc. is not responsible for printing or clerical errors.

Apple

1 Infinite Loop

Cupertino CA 95014

[www.apple.com](http://www.apple.com)

The Apple logo is a trademark of Apple Inc., registered in the U.S. and other countries. Use of the "keyboard" Apple logo (Option-Shift-K) for commercial purposes without the prior written consent of Apple may constitute trademark infringement and unfair competition in violation of federal and state laws.

Apple, the Apple logo, AppleTalk, Mac, Macintosh, QuickTime, Xgrid, and Xserve are trademarks of Apple Inc., registered in the U.S. and other countries. Finder is a trademark of Apple Inc.

Adobe and PostScript are trademarks of Adobe Systems Incorporated.

UNIX is a registered trademark of The Open Group.

Other company and product names mentioned herein are trademarks of their respective companies. Mention of third-party products is for informational purposes only and constitutes neither an endorsement nor a recommendation. Apple assumes no responsibility with regard to the performance or use of these products.

019-1421/2009-05-29

# Contents

7	<b>Preface: About This Guide</b>
7	What's in This Guide
8	Using Onscreen Help
9	Documentation Map
10	Viewing PDF Guides Onscreen
10	Printing PDF Guides
10	Getting Documentation Updates
11	Getting Additional Information
12	<b>Chapter 1: Understanding the Print Service</b>
13	Overview of Network Printing
13	Without the Print Service
14	With the Print Service
15	Supported Printers
16	Supported Clients
17	Workload Distribution Using Printer Pools
17	Things to Consider When Creating a Printer Pool
17	Multiple Network Interface Support
17	Security Considerations
18	Tools for Managing the Print Service
18	Server Admin
18	Workgroup Manager
19	Command-Line Tools
20	<b>Chapter 2: Setting Up the Print Service</b>
20	Setup Overview
21	Planning for the Print Service
21	Print Service Performance
21	Print Service Limitations
21	Print Service Security
22	Turning the Print Service On
22	Securing the Print Service
22	Configuring Print SACLs

23	Configuring Kerberos
24	Setting Up the Print Service
24	Configuring Print Queues
25	Configuring Print Settings
26	Starting the Print Service
27	Advertising an LPR Queue Using Bonjour
27	Listing an LPR Queue in Open Directory
28	Creating a Printer Pool
29	Setting Print Quotas
29	Using Workgroup Manager to Specify User Print Quotas
30	Using Server Admin to enforce Print Quotas for a Queue
30	Restarting a User's Print Quota

## 32 Chapter 3: Setting Up Printing for Clients

32	About PPD Files
32	Viewing PPD Files
33	Mac OS X Clients
33	Adding an IPP Print Queue on Mac OS X Clients
34	Adding an LPR Print Queue on Mac OS X Clients
34	Adding a Print Queue Advertised Through Bonjour or Open Directory
34	Troubleshooting
35	Windows Clients
35	Adding a Print Queue on Windows Clients
35	Viewing the Server NetBIOS Name
35	Viewing the Print Queue Name
36	Viewing IPP Queue Identifier
36	Troubleshooting
36	UNIX Clients

## 37 Chapter 4: Managing the Print Service Using Server Admin

37	Managing the Service
37	Checking the Status of the Print Service
38	Turning Off the Print Service
38	Enabling and Disabling Cover Sheets for Print Jobs
39	Managing Print Queues
39	Creating a Print Queue
40	Viewing Print Queue Status
40	Pausing a Print Queue
41	Resuming a Print Queue
41	Changing Print Queue Settings
42	Renaming a Print Queue
43	Deleting a Print Queue
44	Setting Up a Print Queue for Windows (SMB) Access

44	Managing Print Jobs
44	Monitoring a Print Job
45	Pausing a Print Job
46	Resuming a Print Job
47	Removing a Print Job
47	Managing Print Quotas
47	Suspending Quotas for a Print Queue
48	Managing Print Logs
48	Viewing Print Service and Queue Logs
49	Archiving Print Service Logs
51	<b>Chapter 5: Solving Print Service Problems</b>
51	If the Print Service Doesn't Start
51	If a User Can't Add a Print Queue
52	If a User Can't Print
52	If Jobs in a Print Queue Don't Print
52	If a Print Queue Becomes Unavailable
52	If Windows Users Can't Print
53	<b>Appendix A: Command-Line Parameters for the Print Service</b>
53	Available Print Service Settings
56	<b>Index</b>



# About This Guide

This guide describes the print service you can set up using Mac OS X Server. It also explains how to configure printing on Mac OS X client computers.

Mac OS X Server enables you to configure print service to access a printer on the network or on its USB port, and share it as a queue or class (printer pool) to client computers.

Print service relies on Common Unix Printing System (CUPS) for spooling, queue and job control, security, and error feedback. Print service provides sharing of print queues over Internet Printing Protocol (IPP) and Line Printer Remote (LPR) via CUPS, and SMB via Samba 3.0.

Print service lets Mac OS X Server clients print documents in a flexible, managed printing environment over a network. You can assign users specific printers for printing tasks and manage access to other printers through authentication or user quotas. You can also manage printer use more effectively by balancing the load across a pool of printers handling the same queue.

## What's in This Guide

This guide includes the following sections:

- Chapter 1, “Understanding the Print Service,” explains printing concepts and terms.
- Chapter 2, “Setting Up the Print Service,” includes everything you need to set up and configure print service.
- Chapter 3, “Setting Up Printing for Clients,” on page 32, provides information about configuring client computers to print.
- Chapter 4, “Managing the Print Service Using Server Admin,” provides step-by-step information for ongoing print server maintenance, administration, and monitoring.
- Chapter 5, “Solving Print Service Problems,” describes common problems and provides information on what to do if you encounter problems while printing.

- Appendix A, “Command-Line Parameters for the Print Service,” provides additional command-line parameters for print service.

**Note:** Because Apple periodically releases new versions and updates to its software, images shown in this book may be different from what you see on your screen.

## Using Onscreen Help

You can get task instructions onscreen in Help Viewer while you’re managing Mac OS X Server. You can view help on a server, or on an administrator computer. (An administrator computer is a Mac OS X computer with Mac OS X Server administrator software installed on it.)

### To get the most recent onscreen help for Mac OS X Server:

- Open Server Admin or Workgroup Manager and then:
  - Use the Help menu to search for a task you want to perform.
  - Choose Help > Server Admin Help or Help > Workgroup Manager Help to browse and search the help topics.

The onscreen help contains instructions taken from *Advanced Server Administration* and other administration guides.


### To see the most recent server help topics:

- Make sure the server or administrator computer is connected to the Internet while you’re getting help.

Help Viewer automatically retrieves and caches the most recent server help topics from the Internet. When not connected to the Internet, Help Viewer displays cached help topics.

## Documentation Map

Mac OS X Server has a suite of guides that cover management of individual services. Each service may depend on other services for maximum utility. The documentation map below shows some related guides that you may need in order to fully configure print service to your specifications. You can get these guides in PDF format from the Mac OS X Server Resources website at [www.apple.com/server/macosx/resources/](http://www.apple.com/server/macosx/resources/).



## Viewing PDF Guides Onscreen

While reading the PDF version of a guide onscreen:

- Show bookmarks to see the guide's outline, and click a bookmark to jump to the corresponding section.
- Search for a word or phrase to see a list of places where it appears in the guide. Click a listed place to see the page where it occurs.
- Click a cross-reference to jump to the referenced section. Click a web link to visit the website in your browser.

## Printing PDF Guides

If you want to print a guide, you can take these steps to save paper and ink:

- Save ink or toner by not printing the cover page.
- Save color ink on a color printer by looking in the panes of the Print dialog for an option to print in grays or black and white.
- Reduce the bulk of the printed document and save paper by printing more than one page per sheet of paper. In the Print dialog, change Scale to 115% (155% for *Getting Started*). Then choose Layout from the untitled pop-up menu. If your printer supports two-sided (duplex) printing, select one of the Two-Sided options. Otherwise, choose 2 from the Pages per Sheet pop-up menu, and optionally choose Single Hairline from the Border menu. (If you're using Mac OS X v10.4 or earlier, the Scale setting is in the Page Setup dialog and the Layout settings are in the Print dialog.)

You may want to enlarge the printed pages even if you don't print double sided, because the PDF page size is smaller than standard printer paper. In the Print dialog or Page Setup dialog, try changing Scale to 115% (155% for *Getting Started*, which has CD-size pages).

## Getting Documentation Updates

Periodically, Apple posts revised help pages and new editions of guides. Some revised help pages update the latest editions of the guides.

- To view new onscreen help topics for a server application, make sure your server or administrator computer is connected to the Internet and click "Latest help topics" or "Staying current" in the main help page for the application.
- To download the latest guides in PDF format, go to the Mac OS X Server documentation website at [www.apple.com/server/macosx/resources/](http://www.apple.com/server/macosx/resources/).
- An RSS feed listing the latest updates to Mac OS X Server documentation and onscreen help is available. To view the feed, use an RSS reader application such as Safari or Mail and go to:

`feed://helposx.apple.com/rss/snowleopard/serverdocupdates.xml`

## Getting Additional Information

For more information, consult these resources:

- *Read Me documents*—get important updates and special information. Look for them on the server discs.
- *Mac OS X Server website* ([www.apple.com/server/macosx/](http://www.apple.com/server/macosx/))—enter the gateway to extensive product and technology information.
- *Mac OS X Server Support website* ([www.apple.com/support/macosxserver/](http://www.apple.com/support/macosxserver/))—access hundreds of articles from Apple’s support organization.
- *Apple Discussions website* ([discussions.apple.com/](http://discussions.apple.com/))—share questions, knowledge, and advice with other administrators.
- *Apple Mailing Lists website* ([www.lists.apple.com/](http://www.lists.apple.com/))—subscribe to mailing lists so you can communicate with other administrators using email.
- *Apple Training and Certification website* ([www.apple.com/training/](http://www.apple.com/training/))—hone your server administration skills with instructor-led or self-paced training, and differentiate yourself with certification.

# Understanding the Print Service

# 1

Use this chapter to learn about Mac OS X Server print service, which helps you set up a managed printing environment on your network.

With a print server, you share printers by setting up print queues that are accessible by users over a network connection. When a user prints to a shared queue, the print job waits on the server until the printer is available or until scheduling criteria are met.

More administrator features are available by using a Mac OS X print server. For example:

- Setting page quotas for individual users on specific print queues
- Keeping logs summarizing printer use

The Mac OS X Server print service is built on top of the standard Mac OS X client printing architecture, which, in turn, is built on the Common UNIX Printing System (CUPS). The print service is based on four common protocols:

- Internet Printing Protocol (IPP)—For printing from Macintosh, Windows, or UNIX computers. Requires CUPS.
- Line Printer Remote (LPR)—For printing from UNIX computers and from Macintosh computers running Mac OS 8.1 or later.
- Server Message Block (SMB)—For printing from Windows computers.

Use the following Mac OS X Server applications to set up and manage the print service:

- **Server Admin.** Use Server Admin to turn on and configure individual file services for each protocol.
- **Workgroup Manager.** Use Workgroup Manager to create share points and set access privileges.
- **Terminal.** Use Terminal to perform most setup and management tasks by entering commands at a command prompt.

## Overview of Network Printing


You can benefit from shared network printing without using a server. However, a quick comparison of network printing with and without a server-based print service shows what a print service can do to make things easier for your users and for you as an administrator.

### Without the Print Service

Providing shared printers to your users, even without using a server, is relatively easy: connect the printers to your network so users can choose a printer that suits their needs.

When a user prints a document, the resulting print job waits in a queue on the user's computer until the printer can accept the job. (In common printing terminology, the job is "spooled to a queue.")

The following illustration shows several users and a single printer without a print server. The print job remains in the user's print queue until the printer becomes available.



Although this way of providing access to printers is easy to set up, it has the following disadvantages:


- Users must make sure their jobs finish printing before they turn off their computers or, in the case of mobile clients, disconnect their computers from the network.
- Error messages from the printer (for example, "out of paper" or "paper jam") go directly to the user currently printing.

- It is difficult for you, as administrator, to track or control how many pages are printed by a user.

## With the Print Service

For better network efficiency, use the print service to set up queues for printers. Users choose from these queues instead of choosing printers directly. When a user prints a document, the resulting print job moves quickly from the queue on the user's computer to the queue on the server.

The following illustration shows several users and a single printer with a print server. The print jobs move from user print queues to the server print queue for better management and efficiency.




This way of providing printer access has advantages over simple network printing:

- Print jobs transfer quickly from client computers to the server's queue, so users can turn off or disconnect their computers soon after sending the print job to the server.
- Printer error conditions are reported on the server rather than on client computers.
- You can easily limit and track the number of pages a user prints on a specific printer.
- You can control when and in what order jobs print.

## Supported Printers

Print service supports the following types of printers:

- PostScript-compatible printers connected to your network that use IPP, LPR, or SMB protocols
- PostScript printers connected to the server through Universal Serial Bus (USB)
- Inkjet (raster) printers connected to the server through USB




Client computers using LPR and SMB use only PostScript to transfer jobs to print queues on the server. However, IPP clients format the job data according to the OEM print driver for the destination printer, either PostScript or binary.

When Mac OS X Server receives a PostScript print job, it sends it to the queue of a PostScript printer (networked or directly connected), or it uses the ps2pdf converter to produce a PDF file for output to an inkjet printer.

## Supported Clients

Any client computer using IPP, LPR, or SMB can print to queues shared through the print service, as shown in the following illustration:



Macintosh computers communicate with printers using IPP or LPR. Windows computers use IPP, LPR, or SMB. UNIX computers use IPP or LPR. For more information about printing from a specific kind of computer, see Chapter 3, “Setting Up Printing for Clients.”

## Workload Distribution Using Printer Pools

Each print service queue you set up is assigned to a single printer. CUPS supports a special queue called a printer class or printer pool, which is essentially a queue with more than one printer assigned to it.

A printer pool offers a number of advantages over single-printer queues in high-volume or high-availability printing environments:

- Print jobs are assigned to the next available printer in the pool, so you can have as many jobs printing simultaneously as you have printers assigned to the pool.
- If a printer assigned to the pool becomes unavailable, the other printers in the pool continue to print waiting jobs.

To set up a printer pool, use Server Admin to configure the print service. For more information, see “To see the most recent server help topics:” on page 8. After creating the pool, add and manage the resulting pool queue in the print service as you would any other queue.

## Things to Consider When Creating a Printer Pool

The purpose of a printer pool is to increase printer use efficiency. A printer pool is not intended to compete with individual printer queues; instead, it is meant to replace them. A good practice is to not share a printer individually when it’s also shared in a pool.

It is also good strategy to group printers of similar make and model so each printer in a pool has the same printing capabilities. For instance, it defeats the purpose of a printer pool if all but one printer is capable of printing color.

**Important:** The capabilities of printers in a printer pool are typically defined by the first printer in the pool list. If the print service assigns a job to a less capable printer in the pool, the job might be rejected by the assigned printer and fail.

## Multiple Network Interface Support

In Mac OS X Server, the print service operates across all interfaces that TCP/IP-based printing protocols are configured for. These include CUPS/IPP, LPR, and SMB.

## Security Considerations

LPR printer queues do not support authentication. The print service relies on the client to provide user information. Although standard Macintosh and Windows clients provide correct information, a malicious user could change the client to submit false information and thereby avoid print quotas.

SMB service supports authentication, which requires users to log in before using SMB printers.

Basic and Digest (MD5) authentication is built into CUPS software on which the print service relies. This authentication method supports IPP.

## Tools for Managing the Print Service

The Workgroup Manager and Server Admin applications provide a graphical interface for managing the print service in Mac OS X Server. In addition, you can manage the print service from the command line by using Terminal.

These applications are included with Mac OS X Server v10.6 and can be installed on another computer with Mac OS X Server v10.6, making that computer an administrator computer. For more information on setting up an administrator computer, see the server administration chapter of *Getting Started*.

### Server Admin

Server Admin provides access to tools you use to set up, manage, and monitor the print service and other services. You use Server Admin to:

- Set up Mac OS X Server as a print server. For instructions, see Chapter 2, “Setting Up the Print Service.”
- Manage and monitor the print service. For instructions, see Chapter 4, “Managing the Print Service Using Server Admin.”

For more information about using Server Admin, see *Server Administration*. This includes information about:

- Opening and authenticating in Server Admin
- Working with specific servers
- Administering services
- Using SSL for remote server administration
- Customizing the Server Admin environment

Server Admin is installed in `/Applications/Server/`.

### Workgroup Manager

Workgroup Manager provides comprehensive management of clients of Mac OS X Server. You use Workgroup Manager to:

- Set up and manage print quotas. For instructions, see Chapter 2, “Setting Up the Print Service.”

For basic information about using Workgroup Manager, see *User Management*. Information includes:

- Opening and authenticating in Workgroup Manager
- Administering accounts
- Customizing the Workgroup Manager environment

Workgroup Manager is installed in `/Applications/Server/`.

## Command-Line Tools

A full range of command-line tools is available for administrators who prefer to use command-driven server administration. For remote server management, submit commands in a Secure Shell (SSH) session. You can enter commands on Mac OS X servers and computers using the Terminal application, located in the `/Applications/Utilities/` folder.

For more information about command-line tools, see *Introduction to Command-Line Administration*.

# Setting Up the Print Service

# 2

Use this chapter to set up print queues and change print service settings.

Use Server Admin or Terminal to set up and configure printers and monitor print queues across your organization. With Server Admin, you can also create printer pools so you can improve the efficiency of clients printing.

## Setup Overview

Here is an overview of the steps for setting up the print service:

**Step 1: Before you begin** For issues you should keep in mind before you set up the print service, read “Planning for the Print Service” on page 21.

**Step 2: Turn the print service on** Before you configure the print service, it must be turned on. See “Turning the Print Service On” on page 22.

**Step 3: Secure print service** For added security you can use SACs to restrict who has administrator access to the print service. Additionally, you can configure Kerberos for the print service. See “Using Onscreen Help” on page 8.

**Step 4: Configure print queues** Use Server Admin to create queues for your printers on the server. Users see these queues as printers. See “Getting Additional Information” on page 11.

**Step 5: Configure print settings** Use Server Admin to specify the default LPR queue and set the print service log options. See “Configuring Print Settings” on page 25.

**Step 6: Start the print service** Use Server Admin to start the print service on the server and make the queues available to clients. See “Starting the Print Service” on page 26.

**Step 7: (Optional) Set print quotas** If you want to limit the number of pages users can print, set print quotas for user accounts and enforce quotas on print queues. See “Setting Print Quotas” on page 29.

**Step 8: Set up client computers** Add, or show your users how to add, server queues to printing setups on their computers. See Chapter 3, “Setting Up Printing for Clients.”

## Planning for the Print Service

Although printer setup is simple, take the time to understand the options available for configuring printers. With careful planning, you can maximize the use of each printer on your network and avoid printing delays. You should note which protocols your clients use for printing. Print service supports LPR, IPP, and SMB protocols.

## Print Service Performance

There are no specific performance guidelines for the print service due to the nature of printing.

Throughput is the combination of the size of the job file (100 KB, 10 MB, 1 GB), the network transfer time between client and server (the speed of any data transfer the computers are capable of for any service), the wait time in the queue (zero to infinity), and the time it takes for the destination printer to image all pages (depends on model, speed of processor, and printer memory).

Little or no processing occurs on the server because print spooling is almost entirely comprised of network and file I/O.

## Print Service Limitations

Consider the following print service limitations when you set up the service:

- Print clients are connected to the server only for the duration of the job data transfer. There is a default limit of 500 concurrent connections from client computers and 100 concurrent connections from any one client computer.
- The number of print queues per server is limited only by the available resources on the server (CPU usage, memory, and file descriptors). Printing through a large number of queues (100 or more) simultaneously will likely result in some performance degradation.

## Print Service Security

For setting up a more secure print service, consider the following:

- The print service supports service access control lists (SACLs). SACLs are used to restrict access to the print service so that only authorized users can print. For more information, see “Viewing PDF Guides Onscreen” on page 10.
- Mac OS X Server v10.6 provides Kerberos support for the print service. Kerberos support is only available over IPP connections. When configured, this Kerberized support (included as part of CUPS 1.3) permits single sign-on authentication for any client that is accessing the server to print.

Kerberos authentication must be configured using the CUPS web interface tools. For more information, see “Printing PDF Guides” on page 10.

## Turning the Print Service On

Before you can configure the print service settings, you must turn the print service on in Server Admin.

**To turn print service on:**

- 1 Open Server Admin and connect to the server.
- 2 Click Settings, then click Services.
- 3 Select the Print checkbox.
- 4 Click Save.

## Securing the Print Service

The print service is often an overlooked part of a security configuration. Important information passes to your networked printers, and it is important that your printers are not misused. To increase print service security, configure SACLs and Kerberos.

### Configuring Print SACLs

You can configure SACLs using Server Admin. SACLs enable you to specify which administrators have access to the print service.

SACLs provide you with greater control over which administrators have access to monitor and manage a service.

Only users and groups listed in an SACL have access to its corresponding service. For example, to give administrator access to users or groups for the print service on your server, add them to the print service SACL.

**To set administrator SACL permissions for the print service:**

- 1 Open Server Admin and connect to the server.
- 2 Click Settings, then click Access.
- 3 Click Administrators.
- 4 Select the level of restriction that you want for the service.
  - To restrict access to all services, select “For all services.”
  - To set access permissions for individual services, select “For selected services below” and then select Print Service from the Service list.
- 5 Click the Add (+) button to open the Users & Groups window.
- 6 Drag users and groups from the Users & Groups window to the list.

7 Set the user's permission.

To grant administrator access, choose Administer from the Permission pop-up menu next to the user name.

To grant monitoring access, choose Monitor from the Permission pop-up menu next to the user name.

8 Click Save.

## Configuring Kerberos

You can configure Kerberos support for the print service using Server Admin or CUPS v1.4 online web tools. The print service will then use the local Kerberos server to authorize clients to print.

For your client computers to use Kerberos with the print service, the clients must be part of the same Kerberos realm. For information on how to join your client computers to a Kerberos realm, see *Open Directory Administration*.

In addition to joining the Kerberos realm, client computers must also use CUPS online web tools to configure Kerberos settings. The steps for configuring CUPS are the same on client and server computers.

### To configure Kerberos using Server Admin:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Settings.
- 5 Select the "Require Single-Sign On authentication (Kerberos v5)" checkbox.
- 6 Click Save.

### To configure Kerberos using CUPS online web tools:

- 1 Open Safari browser.
- 2 Navigate to the CUPS online web administration tool at <http://localhost:631>.
- 3 Click the Administration tab.
- 4 Under Server Settings, select the "Use Kerberos authentication" checkbox.
- 5 Click Change Settings and authenticate if prompted.

The print service restarts and Kerberos is enabled.

You can also edit the configuration file in CUPS by clicking Edit Configuration File in the Administration tab to open the `etc/cups/cupsd.conf` file. Change the default authentication type from Basic to Negotiate, as shown:

```
# Default authentication type, when authentication is required...
DefaultAuthType Negotiate
```

## Setting Up the Print Service

This section explains each print service setting.

You set up the print service by configuring the following settings in Server Admin:

- **Queues.** Create and configure print queues and printer pools, and enforce print quotas.
- **Settings.** Specify the default queue for LPR, determine how much information is recorded in the print log, and set the maximum log size.

The following subsections describe how to configure these settings and how to start up the print service when you finish.

### Configuring Print Queues

Use Queues settings to configure print queues that network printers can share.

**To configure Queues settings:**

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Click the Add (+) button to add a print queue for a specific printer; then select the protocol used by the printer the queue is created for from the pop-up menu.
  - For an LPR printer, enter the printer IP address or DNS name in the Printer Address field and click OK.  
If you don't want to use the printer default queue, deselect "Use default queue on server," enter a queue name, and click OK.
  - For an Open Directory printer, select the printer in the list and click OK.
- 6 Select the queue you added to the queue list.  
To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.
- 7 In the Sharing Name field, enter the queue name you want clients to see.  
Make sure the name is compatible with naming restrictions imposed by your clients. For example, some LPR clients do not support names that contain spaces, and some Windows clients restrict names to 12 characters. Queue names shared using LPR or SMB must not contain characters other than A–Z, a–z, 0–9, and \_ (underscore).

**Note:** Changing the Sharing Name also changes the queue name that appears in Print & Fax preferences on the server.

- 8 If you want to enforce the print quotas you establish for users in Workgroup Manager, select the “Enforce quotas for this queue” checkbox.
- 9 If you want the printer to add a cover sheet to every job, choose the title of the cover sheet from the Cover Sheet pop-up menu; otherwise, choose None.
- 10 Select the printing protocols your client computers use.  
If you select SMB, make sure you start SMB service.
- 11 Click Save.

## Configuring Print Settings

Use the print service settings in Server Admin to specify a default LPR queue for the server and to set print logging options.

The print service keeps a general service log and individual logs for each shared queue. When a log is archived, new events are recorded in a new, empty log file. You can also specify the level of detail in the logs and how often the logs are archived.

### To configure the print service settings:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Settings.
- 5 Select “Archive server log.”  
If you don’t want to archive server logs, deselect the “Archive server log” checkbox.
- 6 If you want to archive the log, from the Maximum log size pop-up menu choose the maximum size that the log file can grow to before it is archived.
- 7 From the Log Level pop-up menu, choose the amount of detail to be recorded in the log file.
- 8 Click Save.

Current and archived logs are stored in `/Library/Logs/PrintService/`.

### From the command line:

- To view a setting:

```
$ sudo serveradmin settings print:setting
```
- To view a group of settings for a print queue:

```
$ sudo serveradmin settings print:queuesArray:_array_id:queue-id:*
```

You can view a group of settings that have part of their names in common by entering as much of the name as you want, stopping at a colon (:), and entering an asterisk (\*) as a wildcard for the remaining parts of the name.

- To list all settings:

```
$ sudo serveradmin settings print
```

- To change a setting:

```
$ sudo serveradmin settings print:setting = value
```

- To change several settings:

```
$ sudo serveradmin settings
print:setting = value
print:setting = value
print:setting = value
[...]
Control-D
```

Parameter	Description
<i>queue-id</i>	CUPS queue ID (for example, <id> or _192_216_3_45).
<i>setting</i>	A print service setting.
<i>value</i>	A relevant value for the setting.

For more information about command-line parameters, see “Available Print Service Settings” on page 53. For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Starting the Print Service

Use Server Admin to start the print service. After you start the print service, it restarts when the server is restarted.

### To start the print service:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Start Print (below the Servers list).

### From the command line:

- To start the print service:

```
$ sudo serveradmin start print
```

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Advertising an LPR Queue Using Bonjour

You can make it easier for users to find shared LPR queues by advertising them using Bonjour.

### To advertise a queue using Bonjour:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Select the queue you want to advertise.
- 6 Under LPR in the Protocol section, select “Show name in Bonjour.”
- 7 Click Save.

## Listing an LPR Queue in Open Directory

You can make it easier for users to find shared LPR queues by listing them in Open Directory. If you include the PostScript Printer Description (PPD) printer model name in the directory, users can choose the exact printer model they want.

### To list a queue in Open Directory:

- 1 If you haven't done so, create the queue.  
For more information, see “Creating a Print Queue” on page 39.
- 2 Open Workgroup Manager.
- 3 If you don't see the Inspector buttons, choose Workgroup Manager > Preferences and select “Show All Records tab and inspector.”
- 4 If necessary, switch to the correct directory domain.
- 5 Click the All Records button (which looks like a bull's-eye, next to the Users, Groups, and Computers buttons).
- 6 From the pop-up menu below the All Records button, choose Printers and click New Record.
- 7 In the attribute list, select RecordName (with “untitled\_1” next to it) and click Edit.
- 8 In the Text field, enter the name you want your users to see when they're browsing for the printer and click OK.

- 9 Click New Attribute and choose PrinterLPRHost from the Attribute Name pop-up menu.
- 10 In the Text field, enter the IP address or DNS name of the server that hosts the queue, and click OK.
- 11 Click New Attribute, choose PrinterLPRQueue from the pop-up menu, enter the queue name in the Text field, and click OK.
- 12 If you want to specify the printer model, click New Attribute, choose Printer Type from the pop-up menu, enter the model name, and click OK.

**Note:** Make sure the model name you enter exactly matches the value of the `*modelName` attribute in the PPD file. To confirm the value of this attribute, try either of the following:

- Open Print & Fax preferences and click Printing; click the Add (+) button, click IP Printer, choose the printer protocol from the Protocol pop-up menu, and find the model name in the Print Using pop-up menu.
- Make a copy of the PPD file, use the `gunzip` command in Terminal to decompress it, then open it in TextEdit or another text editor and search for `**modelName.` The PPD files are in `/Library/Printer/PPDs/Contents/Resources/en.lproj.`

- 13 Click Save.

## Creating a Printer Pool

You can create a printer pool using Server Admin or Terminal.

### To create a printer pool:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Create two or more print queues.

For more information about creating a print queue, see “Getting Additional Information” on page 11.

**Important:** Pooled printers must be the same make and model so that output is consistent. Users might lose printer functionality if fully-featured printers are pooled with printers having fewer features.

- 6 Select printers from the Queues list.  
The Create Printer Pool button is activated.
- 7 Click Create Printer Pool.

- 8 Enter a name to identify the print pool.  
This name becomes the sharing name, by which users identify the print pool.
- 9 Click OK.
- 10 Select the printing protocols your client computers use.  
If you select SMB, make sure you start SMB service.
- 11 If you want to enforce the print quotas you establish for users in Workgroup Manager, select "Enforce quotas for this queue."
- 12 If you want the printer to create a cover sheet, choose the title of the cover sheet from the Cover Sheet pop-up menu; otherwise, choose "None."
- 13 Click Save.

## Setting Print Quotas

A print quota is the total number of pages a user is permitted to print during a specified time period. When a user has printed the specified number of pages, he or she cannot print again until the quota period ends and the quota is automatically renewed. Alternatively, you can explicitly renew the quota.

For each user, you can set a single quota that covers all printers they use, or you can set individual quotas for each printer:

- In the case of a single quota, every page printed counts against a user's quota, regardless of the printer used.
- In the case of per-queue quotas, you can vary the quota from printer to printer or you can choose not to enforce quotas on some printers while restricting the use of others.

The procedure for setting up a print quota involves two steps:

- Use Workgroup Manager to specify the quota and time period for each user.
- Use Server Admin to set print service to enforce quotas for individual queues.

## Using Workgroup Manager to Specify User Print Quotas

Use Workgroup Manager to specify print quotas for individual users.

**To set a user's quota:**

- 1 Open Workgroup Manager, click Accounts, and select the user.
- 2 Click Print, and choose from the following:
  - To set one quota for all queues, select All Queues, then enter the number of pages and the number of days after which the quota is restarted.
  - To set a quota for a specific queue, select Per Queue, choose the queue from the pop-up menu, then click Limit to and enter the quota and quota period.

If the queue is not in the list, click Add, change “untitled” in the Queue Name field to the queue name, enter the IP address or DNS name of the server hosting the queue, and then enter the user’s page quota and quota period.

- 3 Click Save.

The quotas are not enforced until you use Server Admin to turn on quota enforcement for specific queues.

## Using Server Admin to enforce Print Quotas for a Queue

Users are not subject to print quotas you set for them in Workgroup Manager until you also use Server Admin to turn on quota enforcement for specific print queues in the print service.

**Important:** When you enforce a print quota on a queue, users can’t print to the queue unless they have a valid, unexpired quota defined for them in Workgroup Manager.

### To enforce quotas for a print queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Select a queue from the queue list.

To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.

- 6 Select the “Enforce quotas for this queue” checkbox.
- 7 Click Save.

### From the command line:

- To set quota enforcement for a queue:

```
$ sudo serveradmin settings print:queuesArray:_array_id:<id>:quotas
    Enforced
```

For more information about command-line parameters, see “Queue Data Array” on page 54. For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Restarting a User’s Print Quota

Use Workgroup Manager to restart a user’s quota period or change the user’s page quota.

**To restart quotas for a print queue:**

- 1 Open Workgroup Manager, click Accounts, and select the user.
- 2 Click Print and select All Queues or Per Queue.
- 3 Restart the quota period by clicking Restart Print Quota.
- 4 To change the number of pages permitted during the current quota period, enter a new value in the “Limit to” field.

**Note:** If you change the duration of a user’s print quota, the print service restarts the quota’s period.

- 5 Click Save.

# Setting Up Printing for Clients

# 3

Use this chapter to set up clients to use the printers offered by your print service.

Before client computers can access network printers, they must be configured properly. The print service supports three classes of clients:

- Mac OS X clients
- Windows clients
- UNIX clients

## About PPD Files

A PostScript Printer Description (PPD) file contains specialized information about a specific printer model. Your users need the PPD file to take advantage of a printer's special features and capabilities. Without the correct PPD file, users can't do things such as choose from multiple paper trays, use special paper sizes, or print on both sides of the page.

## Viewing PPD Files

Mac OS X and Mac OS X Server come with PPD files already installed for most popular printers.

**To view available PPD files:**

- 1 Open Print & Fax preferences.
- 2 Click the Add (+) button and click IP.
- 3 From the Protocol pop-up menu, choose "Internet Printing Protocol – IPP."
- 4 In the Address field, enter the host name or IP address of the printer.
- 5 From the Print Using pop-up menu, choose a vendor.

If you can't find a PPD for the printer you want to use, contact the manufacturer for a PPD installer for that model. As a last resort, try using the Generic PPD file, which enables basic printing on most printers.

The relevant PPD file must be chosen on the client computer when the print queue is added.

## Mac OS X Clients

To use queues offered by a server, Mac OS X users must add the queues to their printer lists using Print & Fax preferences, just as they would to add any other printer. Mac OS X supports LPR printers.

### Adding an IPP Print Queue on Mac OS X Clients

The print service queues you share through IPP appear in the client's Default Browser list in Print & Fax preferences and in the print dialog of all Mac OS X applications.

There are two important advantages to using IPP queues over SMB or LPR PostScript queues:

- After the job is spooled to the server print queue, you can use Print & Fax preferences to monitor the progress of the job and even delete the job from the server.
- When printing to an IPP queue for a non-PostScript printer, you can use the printer's native driver (if installed on your Mac OS X computer) to take advantage of all the printer's features. This option is not available to clients printing to non-PostScript printers shared through LPR or SMB.

#### To add an IPP print queue by IP address or DNS name:

- 1 On the client computer, open Print & Fax preferences.
- 2 Click the Add (+) button and click IP.
- 3 From the Protocol pop-up menu, choose Internet Printing Protocol – IPP.
- 4 In the Address field, enter the server's DNS name or IP address (not the printer's name or address).
- 5 In the Queue field, enter the queue name in the form *printers/queue*, where *queue* is the IPP queue identifier.

To use the server's default queue, leave the Queue field blank.

For information about IPP queue identifier, see "Viewing IPP Queue Identifier" on page 36.

- 6 From the Print Using pop-up menu, choose the printer type.  
If you're not sure of the type, Generic PostScript Printer works for most printing needs.
- 7 Click Add.

If you set up your server to advertise LPR print queues using Bonjour or Open Directory, a client can browse for an LPR queue instead of needing to know the address of the server and the name of the queue when adding a printer.

## Adding an LPR Print Queue on Mac OS X Clients

You can use Print & Fax preferences to add an LPR print queue to a computer's printer list. The way you add an LPR printer depends on whether the printer is shared by IP address or DNS name only, advertised through Bonjour, or listed in Open Directory.

### To add an LPR print queue by IP address or DNS name:

- 1 On the client computer, open Print & Fax preferences.
- 2 Click the Add (+) button and click IP.
- 3 From the Protocol pop-up menu, choose Line Printer Daemon – LPD.
- 4 In the Address field, enter the server's DNS name or IP address (not the printer's name or address).
- 5 In the Queue field, enter the queue name.  
To use the server's default queue, leave the Queue field blank.
- 6 From the Print Using pop-up menu, choose the printer type.  
If you're not sure of the type, Generic PostScript Printer works for most printing needs.
- 7 Click Add.

If you set up your server to advertise LPR print queues using Bonjour or Open Directory, a client can browse for an LPR queue instead of needing to know the address of the server and the name of the queue when adding a printer.

## Adding a Print Queue Advertised Through Bonjour or Open Directory

### To add a print queue that is advertised through Bonjour or Open Directory:

- 1 On the client computer, open Print & Fax preferences.
- 2 Click the Add (+) button and click Default.
- 3 Select the print queue from the list.  
If the Location field is blank, enter the location of the printer in the Location field.
- 4 From the Print Using pop-up menu, choose the printer type.  
If you're not sure of the type, Generic PostScript Printer works for most printing needs.
- 5 Click Add.

For help with advertising a printer using Bonjour, see "Advertising an LPR Queue Using Bonjour" on page 27.

For help with listing a printer in Open Directory, see "Listing an LPR Queue in Open Directory" on page 27.

## Troubleshooting

If a Mac OS X client is having trouble printing, see Chapter 5, "Solving Print Service Problems."

## Windows Clients

The print service supports Windows clients via SMB, IPP, or LPR.

Most versions of Windows support SMB to some extent. Additionally, the print service can support Windows clients through IPP and LPR, with IPP and LPR support being built into Windows XP and Vista. LPR client support for Windows 95, Windows 98, and Windows Millennium Edition (ME) is available through third party add-ons.

In general, Windows does not support AppleTalk printing, except for Windows NT and Windows 2000 servers.

To enable printing by Windows users who submit jobs using SMB, make sure that the SMB service is running and that print queues are available for SMB use.

### Adding a Print Queue on Windows Clients

Windows users can use the Add Printer Wizard to connect to Mac OS X Server print queues. The wizard allows users to browse the network for a printer or to specify the printer address using the universal naming convention (UNC) format:

```
\\servername\printqueuname
```

The *servername* is the NetBIOS name of the PDC server or a Windows domain member server where you want the user share point stored. For more information, see “Viewing the Server NetBIOS Name” on page 35.

The *printqueuname* is the sharing name assigned to the print queue on the server. For more information, see “Viewing the Print Queue Name” on page 35.

### Viewing the Server NetBIOS Name

Use Server Admin to view the server name for the SMB service.

**To view the server name:**

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 From the expanded Servers list, select SMB.
- 4 Click Settings, then click General.
- 5 Look at the Computer Name field.

### Viewing the Print Queue Name

Use Server Admin to view the print queue sharing name.

**To view the print queue sharing name:**

- 1 Open Server Admin and connect to the server.

- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 From the expanded Servers list, select Print.
- 4 Click Queues.
- 5 Look at the Sharing Name column.

### Viewing IPP Queue Identifier

When installing a IPP printer you might be required to enter the IPP queue identifier. You can view a printers IPP queue identifier using Server Admin.

#### To view the IPP queue identifier:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Select the queue from the list and note the printer queue identifier, labeled as Printer.

### Troubleshooting

If a Windows client is having trouble printing, see Chapter 5, “Solving Print Service Problems.”

### UNIX Clients

UNIX computers support LPR for connecting to networked printers without the installation of more software.

# Managing the Print Service Using Server Admin

# 4

Use this chapter to perform routine management tasks for the print service after it is running.

You can manage print service using Server Admin. Server Admin allows you to verify the overall status of the service and print queues, to review logs, and to view print jobs.

## Managing the Service

This section describes day-to-day tasks you might perform to keep the print service running efficiently, to stop the service, and to set up print job cover sheets.

## Checking the Status of the Print Service

You can use Server Admin to monitor the print service.

**To check the status of the print service:**

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 From the expanded Servers list, select Print.
- 4 Click Overview to see if the print service is running, the time it started if it is running, and the number of queues and waiting print jobs.
- 5 Click Logs.  
Use the View pop-up menu to select a log.  
Use the Filter field located in the upper right to search for specific entries.
- 6 Click Job Status and choose a queue from the “Jobs on Queue” pop-up menu to see a list of print jobs waiting in each queue.
- 7 Click Queues to see the status of print queues.

**From the command line:**

- To see summary status of the print service:

```
$ sudo serveradmin status print
```

- To see detailed status of the print service:

```
$ sudo serveradmin fullstatus print
```

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Turning Off the Print Service

You can use Server Admin to stop the print service.

**To stop the print service:**

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 From the expanded Servers list, select Print.
- 4 Click Stop Print (below the Servers list).
- 5 Click Stop Now.

**From the command line:**

- To stop the print service:

```
$ sudo serveradmin stop print
```

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Enabling and Disabling Cover Sheets for Print Jobs

You can use Server Admin to enable or disable cover sheets for print jobs.

**To enable or disable cover sheets for print jobs:**

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 From the expanded Servers list, select Print.
- 4 Click Queues.
- 5 From the queue list, select the queue you want to edit.

To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.

- 6 If you want the printer to create a cover sheet, choose the title of the cover sheet from the Cover Sheet pop-up menu; otherwise, choose “None.”
- 7 Click Save.

## Managing Print Queues

This section tells you how to perform day-to-day print queue management.

### Creating a Print Queue

You can share any printer that is set up in a print queue on the server. You create print queues using Server Admin.

#### To create a shared print queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.

The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Click the Add (+) button to add a print queue for a specific printer; then choose the protocol used by the printer the queue is created for from the pop-up menu.
  - For an LPR printer, enter the printer IP address or DNS name in the Printer Address field and click OK.

If you don't want to use the printer default queue, deselect “Use default queue on server;” enter a queue name, and click OK.
  - For an Open Directory printer, select the printer in the list and click OK.
- 6 Select the queue you have added to the queue list.

To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.

**Note:** Changing the Sharing Name also changes the queue name that appears in Print & Fax preferences on the server.
- 7 In the Sharing Name field, enter the queue name you want clients to see.

Make sure the name is compatible with naming restrictions imposed by your clients. For example, some LPR clients do not support names that contain spaces, and some Windows clients restrict names to 12 characters. Queue names shared using LPR or SMB must not contain characters other than A–Z, a–z, 0–9, and \_ (underscore).
- 8 To enforce the print quotas you establish for users in Workgroup Manager, select the “Enforce quotas for this queue” checkbox.

- 9 If you want the printer to create a cover sheet, choose the title of the cover sheet from the Cover Sheet pop-up menu; otherwise, choose “None.”
- 10 Select the printing protocols your clients use.  
If you select SMB, make sure you start SMB service.
- 11 Click Save.

## Viewing Print Queue Status

You can use Server Admin to see the current status of print queues. The Queues pane shows all settings for the print queues configured for the server. This list includes the queue name, printer type, and how the printer is shared.

### To view queue status:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues to see the list of print queues on the server.

### From the command line:

- To list the print service queues:

```
$ sudo serveradmin command print:command = getQueues
```

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Pausing a Print Queue

To prevent waiting jobs from printing, you can use Server Admin to pause the queue that contains them.

New jobs continue to be added to the queue but do not print until you resume printing for the queue. When you resume the queue, any print job that was interrupted is reprinted from the beginning.

### To pause a queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Job Status to see a list of print queues and print jobs on the server.
- 5 Select the queue and then click Pause (below the list).

The Status displays as “Stopped.”

#### From the command line:

- To pause a queue:

```
$ sudo serveradmin command
print:command = setQueueState
print:state = PAUSED
print:namesArray:_array_index:0 = queue
Control-D
```

Parameter	Description
<code>queue</code>	The name of the queue. To find the name of the queue, use the <code>getQueues</code> command and look for the value of the <code>printer</code> setting. See “Viewing Print Queue Status” on page 40.

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Resuming a Print Queue

You can use Server Admin to resume printing all waiting jobs in a paused queue.

#### To resume a print queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Job Status to see a list of print queues on the server.

The Status column indicates if the print queue is stopped.

- 5 Select a paused queue and click Resume (below the list).

Jobs that were on hold remain on hold. If a printing job was interrupted when you paused the queue, that job prints again from the beginning.

## Changing Print Queue Settings

You can use Server Admin to view and change the configuration of a print queue.

**Note:** When you change the configuration of a queue, the queue can become unavailable to users. If this happens, users must set up their computers to use the queue again.

#### To change the settings of a print queue:

- 1 Open Server Admin and connect to the server.

- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 From the queue list, select the print queue you want to change.  
To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.
- 6 Make changes, then click Save.

#### From the command line:

- To change print queue settings:

```
$ sudo serveradmin settings print:queuesArray:_array_id:settings = value
```

Parameter	Description
<i>settings</i>	The name of the setting.
<i>value</i>	The value of the setting.

For more information about command-line parameters, see “Queue Data Array” on page 54. For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Renaming a Print Queue

When you add a printer in Print & Fax preferences, the default name of the new queue is the name of the associated printer. You can change this name to help users choose the right printer or to comply with naming conventions imposed by the protocols your clients use.

**Note:** If you change the name of a print queue that is being shared, users must set up their computers again to use the queue with its new name. New jobs that users send to the queue with the old name are not printed.

#### To rename a queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 In the queue list, select the print queue you want to change.  
To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.

- 6 In the Sharing Name field, enter a new name.
- 7 Click Save.

Changing the sharing name for the queue does not change its underlying Print & Fax preferences queue name.

#### From the command line:

- To rename a queue:

```
$ sudo serveradmin settings print:queuesArray:_array_
id:queue:sharingList:_array_index:1:service = name
```

Parameter	Description
<code>queue</code>	The name of the queue. To find the name of the queue, use the <code>getQueues</code> command and look for the value of the <code>printer</code> setting. See “Viewing Print Queue Status” on page 40.
<code>name</code>	The new name of the queue.

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Deleting a Print Queue

When you delete a print queue, jobs in the queue are also deleted. If a job is printing, it is canceled immediately. To permit existing jobs to finish printing while preventing new jobs from arriving, disable the sharing protocols in the queue settings and wait until all jobs finish printing before deleting the queue.

#### To delete a print queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Select the queue from the queue list.  
To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.
- 6 Click the Delete (–) button.
- 7 Click OK, then click Save.

## Setting Up a Print Queue for Windows (SMB) Access

You can allow Windows clients to access an existing print queue via SMB, the standard Windows protocol for printer sharing. You use Server Admin to configure queues for shared printers on the server.

### To provide SMB access to a print queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.
- 5 Select the print queue in the list.
- 6 Make sure Sharing Name is compatible with SMB sharing.

Changing the Sharing Name also changes the Print & Fax preferences queue name on the server. Names of queues shared using SMB should be 15 characters maximum and should not contain characters other than A--Z, a--z, 0--9, and \_ (underscore).

Sharing Name is the queue name, which users see as the name of a printer. Changing Sharing Name does not affect the printer name on the server, which is shown above Sharing Name. You can edit the printer name, kind (model), and location by using Print & Fax preferences.

To avoid conflicts, make sure Sharing Name is not the same as any SMB share point name.

- 7 For Protocol, select SMB.
- 8 Click Save.

SMB service must be running to provide SMB access to print queues. For more information, see *File Server Administration*.

## Managing Print Jobs

This section tells you how to perform day-to-day management of print jobs.

### Monitoring a Print Job

You can monitor individual print jobs using Server Admin.

#### To view a print job:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.

- 3 Click Print.
- 4 Click Job Status.
- 5 From the Jobs on Queue pop-up menu, choose a queue.

Jobs are listed in priority order and include the name of the user who submitted each job, the name of the job, its size, the number of sheets to be printed, the status of the job, and the number of pages in the job. (If the page column is not visible, scroll to see it.)

### Pausing a Print Job

When you put a print job on hold, it is not printed until you resume it. If the job has started to print, printing stops and the job remains in the queue.

While the print job is paused, other jobs in the queue that are not on hold continue to print. When you resume the job, printing starts from the beginning of the job.

#### To pause a print job:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Job Status.
- 5 From the Jobs on Queue pop-up menu, choose a queue.
- 6 Select a job and click Pause (below the list).

Shift-click or Command-click to select multiple jobs.

#### From the command line:

- To hold a print job:

```
$ sudo serveradmin command
print:command = setJobState
print:status = HOLD
print:jobsArray:_array_index:0:printer = queue
print:jobsArray:_array_index:0:idsArray:_array_index:0 = jobid
Control-D
```

Parameter	Description
<code>queue</code>	The name of the queue. To find the name of the queue, use the <code>getQueues</code> command and look for the value of the <code>printer</code> setting. See “Viewing Print Queue Status” on page 40.
<code>jobid</code>	The ID of the job. To find the ID of the job, use the <code>getJobs</code> command and look for the value of the <code>jobId</code> setting.

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Resuming a Print Job

When a print job is paused, it does not print until you resume the job. When you resume the job, printing starts from the beginning.

**Note:** If you put the print queue on hold, you must resume the queue to print the job. For more information, see “Resuming a Print Queue” on page 41.

### To resume a print job:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Job Status.
- 5 From the Jobs on Queue pop-up menu, choose a queue.
- 6 Select the job and click Resume (below the list).

Shift-click or Command-click to select multiple jobs.

The job prints after all other jobs in the queue that have the same priority are printed.

### From the command line:

- To release a job for printing by changing its state to `pending`:

```
$ sudo serveradmin command
print:command = setJobState
print:status = PENDING
print:jobsArray:_array_index:0:printer = queue
print:jobsArray:_array_index:0:idsArray:_array_index:0 = jobid
Control-D
```

Parameter	Description
<code>queue</code>	The name of the queue. To find the name of the queue, use the <code>getQueues</code> command and look for the value of the <code>printer</code> setting. See “Viewing Print Queue Status” on page 40.
<code>jobid</code>	The ID of the job. To find the ID of the job, use the <code>getJobs</code> command and look for the value of the <code>jobId</code> setting.

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Removing a Print Job

You can use Server Admin to remove a print job.

### To remove a print job:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Job Status.
- 5 From the Jobs on Queue pop-up menu, choose a queue.
- 6 Select the job and click Remove (below the list).

Pages already sent to the printer continue to print even after you remove the job.

## Managing Print Quotas

This section tells you how to perform day-to-day management of print quotas.

### Suspending Quotas for a Print Queue

You can use Server Admin to enforce and suspend print quotas for specific queues. Suspending quotas for a print queue permits all users to have unlimited printing to the queue.

#### To suspend quotas for a print queue:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Queues.

- 5 From the queue list, select the print queue you want to change.  
To verify that you selected the correct queue, make sure the queue name matches the name next to Printer.
- 6 Deselect “Enforce quotas for this queue.”
- 7 Click Save.

**From the command line:**

- To disable quotas:

```
$ sudo serveradmin settings print:queuesArray:_array_  
id:queue:quotasEnforced = no
```

Parameter	Description
<code>queue</code>	The name of the queue. To find the name of the queue, use the <code>getQueues</code> command and look for the value of the <code>printer</code> setting. See “Viewing Print Queue Status” on page 40.

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Managing Print Logs

This section tells you how to view and archive the print service and queue logs.

### Viewing Print Service and Queue Logs

The print service keeps two types of logs: a print service log and individual print queue logs.

- The print service log records the time of events such as when the print service starts and stops and when a print queue is put on hold.
- A print queue log records information such as the name of users who submitted jobs, the size of each job, and errors associated with a job.

You can view print service logs using Server Admin.

**To view print service logs:**

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.  
The list of services appears.
- 3 Click Print.
- 4 Click Logs.

Use the View pop-up menu to select the desired log.

Use the Filter field to search for specific entries.

#### From the command line:

- To view the latest entries in a log:

```
$ tail log-file
```

The following are log files for the print service:

- /var/log/cups/error\_log (CUPS general message log)
- /var/log/cups/access\_log (CUPS access log)
- /var/log/cups/page\_log (CUPS page log)
- /Library/Logs/PrintService/PrintService.admin.log

Server Admin Print log: logs all Print administrative actions issued from Server Admin.

- To view log paths:

```
$ sudo serveradmin command print:command = getLogPaths
```

The computer responds with the following output:

```
print:logPathsArray:_array_index:0:name = "Print Service Admin log"
print:logPathsArray:_array_index:0:path = "/Library/Logs/PrintService/
PrintService_admin.log"
print:logPathsArray:_array_index:1:name = "CUPS: error_log"
print:logPathsArray:_array_index:1:path = "/var/log/cups/error_log"
print:logPathsArray:_array_index:2:name = "CUPS: access_log"
print:logPathsArray:_array_index:2:path = "/var/log/cups/access_log"
print:logPathsArray:_array_index:3:name = "CUPS: page_log"
print:logPathsArray:_array_index:3:path = "/var/log/cups/page_log"
```

For information about `tail` and `serveradmin`, see their man pages. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

## Archiving Print Service Logs

You can use Server Admin to specify how large print service logs get before they are archived and new logs are started.

The print service archives logs following the CUPS model. When a print service log file reaches the maximum size, the print service moves the file to `log_name.0`, where `log_name` is the name of the log file, and starts a new log file with the previous name (`log_name`). If an archive exists, the print service overwrites it.

#### To specify the maximum size of archive logs:

- 1 Open Server Admin and connect to the server.
- 2 Click the triangle at the left of the server.

The list of services appears.

- 3 Click Print.
- 4 Click Settings.
- 5 From the Log Level pop-up menu, choose a level of log reporting.  
Choosing to only log errors produces a less verbose log of events in the log file than choosing to log events at the debug level.
- 6 Select the “Archive server log” checkbox.  
This activates the Maximum log size pop-up menu.
- 7 From the Maximum log size pop-up menu, choose the maximum log size, in megabytes.  
To increase log history, set the maximum log size to a higher value.
- 8 Click Save.

**From the command line:**

- To set the archive log size:

```
$ sudo serveradmin settings print:queuesArray:_array_
    id:queue:serverLogArchiveSizeMB = size
```

Parameter	Description
<i>queue</i>	The name of the queue. To find the name of the queue, use the <code>getQueues</code> command and look for the value of the <code>printer</code> setting. See “Viewing Print Queue Status” on page 40.
<i>size</i>	The size of the archive log. Default = 1; maximum log size Range = 1–512 MB

For information about `serveradmin`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

# Solving Print Service Problems

# 5

## Use this chapter to troubleshoot print service problems.

If you are experiencing the following print service problems, see the related section of this chapter for suggestions to alleviate the problem.

- The print service doesn't start
- A user can't add a print queue
- A user can't print
- Jobs in a print queue don't print
- A print queue becomes unavailable
- Windows users can't print

### If the Print Service Doesn't Start

- Verify that the software serial number for the server is entered correctly and has not expired. To check the number, open Server Admin, select your server, then click Server (below your servers name) in the Servers list. To enter an updated serial number, click General Settings, then click General.
- Check the print service log for indications of problems. Open Server Admin, select Print in the Servers list, and click Logs.

### If a User Can't Add a Print Queue

- Make sure print service is running. Open Server Admin and select Print in the Servers list. If the service is not running, click Start Print (below the Server list).
- Verify that the queue is shared correctly. SMB is for Windows users only. LPR is a standard print protocol for Macintosh, UNIX, some Windows computers, and other computers.

## If a User Can't Print

- Make sure the print service is running. Open Server Admin and select Print in the Servers list. If the service is not running, click Start Print (below the Servers list).
- Make sure the queue has been added. On Mac OS X, use Print & Fax preferences to add print queues to the printer list.
- Verify that Mac OS clients have set up TCP/IP correctly.
- Verify that Windows NT 4.x clients have entered the queue name correctly. Use the DNS host name instead of the printer or server TCP/IP address. If the queue doesn't have a DNS name, enter a queue name containing only letters and numbers.

## If Jobs in a Print Queue Don't Print

- Make sure neither the queue nor the jobs in it are on hold. Open Server Admin, select Print in the Servers list, click Job Status, and then choose a queue from the Jobs on the Queue pop-up menu to view the status of jobs.
- Make sure the printer is connected to the server or to the network that the server is connected to.
- Make sure the printer is turned on and that there are no problems with the printer (out of paper, paper jams, and so on).
- Review the print logs for more information. Open Server Admin, select Print in the Servers list, and click Logs.

## If a Print Queue Becomes Unavailable

If you changed a print queue name that is being shared, print jobs that users send to the old queue name are not printed. Users must set up their computers again to use the queue with its new name.

## If Windows Users Can't Print

If Windows NT 4.x clients can't print to the server, make sure the queue name is not the TCP/IP address of the printer or server. Use the DNS host name instead of the printer or server address or, if there is none, enter a queue name containing only letters and numbers. The name of an SMB print queue must not exceed 15 characters.

# Command-Line Parameters for the Print Service

# A

## Available Print Service Settings

To change settings for the print service, use the following parameters with the `serveradmin` tool.

Parameter (print:)	Description
<code>serverLogArchiveEnable</code>	Default = <code>no</code> ; <code>yes</code> enforces log size limits
<code>&lt;queue arrays&gt;</code>	See “Queue Data Array” on page 54
<code>serverLogArchiveSizeMB</code>	Default = 1; maximum log size Range = 1–512 MB
<code>logLevel</code>	Default = <code>info</code> ; for details, see the CUPS documentation.
<code>logLevelNames</code>	Read-only list of valid log level names
<code>defaultLprQueue</code>	Queue-ID of selected default LPR-shared queue
<code>lprQueues</code>	Read-only list of available LPR-shared queues
<code>useRemoteQueues</code>	Default = <code>yes</code> ; <code>no</code> = suppress inclusion of remote queues in queue list
<code>maxClients</code>	Default = 500
<code>maxClientsPerHost</code>	Default = 100

The log size limits apply to all CUPS logs:

- `/var/log/cups/error_log` (CUPS general message log)
- `/var/log/cups/access_log` (CUPS access log)
- `/var/log/cups/error_log` (CUPS page log)

These limits also apply to the following log file:

- `/Library/Logs/PrintService/PrintService.admin.log`  
Server Admin Print log: logs all Print administrative actions issued from Server Admin.

The log level option filters the number of messages written to the following logs:

- `/var/log/cups/error_log`

- /Library/Logs/PrintService/PrintService.admin.log
- /Library/Logs/atprintd/<queue-id>.spool.log

### Queue Data Array

Print service settings include an array of values for each print queue. The array is a set of parameters that define values for each queue.

The array of sharing services now includes IPP. This is the same service as Mac OS X v10.3 printer sharing, now integrated with Mac OS X Server v10.6.

Many of the following parameters are CUPS parameters. For more details about CUPS parameters, see the CUPS documentation.

<id> is a CUPS queue ID (for example, <id> or \_192\_216\_3\_45).

Parameter (print:)	Description
queuesArray:_array_ id:<id>:quotasEnforced	Default = no; yes = enforce quota limits for queue.
queuesArray:_array_ id:<id>:sharingList:_array_ index:0:service	Service name for IPP (CUPS).
queuesArray:_array_ id:<id>:sharingList:_array_ index:1:service	Default = "LPR"; service name for UNIX Line Printer.
queuesArray:_array_ id:<id>:sharingList:_array_ index:2:service	Default = "SMB"; service name for Windows SMB.
queuesArray:_array_id:<id>:shareable	Cannot be changed. Default = yes.
queuesArray:_array_ id:<id>:printerName	Cannot be changed using serveradmin. Default = "<printer-name>."
queuesArray:_array_ id:<id>:printerURI	Format depends on type of printer. Cannot be changed using serveradmin. Default = <uri>; CUPS printer device info.
queuesArray:_array_ id:<id>:registerRendezvous	Default = yes; yes = advertise printer over multicast DNS.
queuesArray:_array_ id:<id>:printerKind	CUPS queue identifier. Cannot be changed using serveradmin.
queuesArray:_array_ id:<id>:sharingName	Name used to advertise queue on network.
queuesArray:_array_ id:<id>:defaultCoverPage	Name of assigned cover page.

The following is an example of a queue array parameter block:

```
print:queuesArray:_array_id:my_printer:quotasEnforced = no
print:queuesArray:_array_id:my_printer:sharingList:_array_index:0:service
    = "LPR"
print:queuesArray:_array_id:my_printer:sharingList:_array_
    index:0:sharingEnable = no
print:queuesArray:_array_id:my_printer:sharingList:_array_index:1:service
    = "SMB"
print:queuesArray:_array_id:my_printer:sharingList:_array_
    index:1:sharingEnable = no
print:queuesArray:_array_id:my_printer:sharingList:_array_
    index:2:sharingEnable = no
print:queuesArray:_array_id:my_printer:shareable = yes
print:queuesArray:_array_id:my_printer:printerName = "Room 3 Printer"
print:queuesArray:_array_id:my_printer:printerURI = "pap://*/Room%20%20
    Printer/LaserWriter"
print:queuesArray:_array_id:my_printer:registerRendezvous = yes
print:queuesArray:_array_id:my_printer:printerKind = "Lexmark_Optr_E310"
print:queuesArray:_array_id:my_printer:sharingName = "Room 3 Printer"
```

**Note:** In the example above, "my\_printer" refers to the CUPS queue id.

# Index

## A

access control lists. *See* ACLs  
 access, printing 14, 21, 22, 23  
 ACLs (access control lists) 21, 22  
 AppleTalk 35  
 archiving print service logs 49  
 authentication 17, 21, 22, 23

## B

Bonjour browsing service 27, 34

## C

clients  
   connections 21  
   overview 7  
   security 17, 21, 23  
   setup 32, 33, 34, 35, 36  
   supported 16  
   *See also* users  
 command-line tools  
   logs 49, 50  
   naming queues 43  
   overview 19  
   pausing queue 41  
   print job management 45, 46  
   print quotas 48  
   settings 25, 42, 53  
   status checking 38, 40  
   stopping service 38  
 Common UNIX Printing System. *See* CUPS  
 configuration  
   access control 22, 23  
   clients 32, 33, 34, 35, 36  
   overview 20  
   print settings 25  
   queues 24, 41  
   Windows users 35, 44  
 cover sheets 38  
 CUPS (Common UNIX Printing System) 12, 17, 18,  
   23, 49, 53

## D

digest authentication 18

directory services 27, 34  
 DNS (Domain Name System) service 33, 34  
 documentation 9, 10  
 Domain Name System. *See* DNS  
 domains, directory 27, 34

## E

error messages. *See* troubleshooting

## H

help, using 8

## I

IPP (Internet Printing Protocol) 12, 18, 33, 35, 36

## J

jobs, print 44, 45, 46, 47, 52  
   *See also* queues, print

## K

Kerberos 21, 22, 23

## L

logs 48, 49, 51, 53  
 LPR (Line Printer Remote) printing  
   adding queues 34  
   advertising with Bonjour 27  
   Open Directory queue 27  
   overview 12  
   security 17  
   Windows users 35

## M

Mac OS X clients 33, 34

## N

naming conventions, queues  
   IPP identifier 36  
   sharing name 24, 42, 44  
   Windows users 35, 52  
 NetBios name 35  
 network printing 13, 14

## O

Open Directory 27, 34

## P

permissions 22  
pool, printer 17, 28  
PPD (Postscript Printer Description) file 28, 32  
Print & Fax preferences 33, 34, 42  
print service  
    access control 14, 21, 22, 23  
    clients supported 16  
    cover sheets 38  
    management tools 18, 37  
    monitoring of 44  
    overview 7, 12, 13, 14  
    pausing 45  
    planning for 21  
    pool creation 28  
    printers supported 15  
    quotas 29, 30, 47  
    removing jobs 47  
    resuming 46  
    settings 24, 25, 53  
    setup 20  
    starting 22, 26, 51  
    status checking 37  
    stopping 38  
    troubleshooting 51, 52  
    workload distribution 17  
    *See also* command-line tools, queues, print  
printer classes. *See* pool, printer  
printer pool. *See* pool, printer  
protocols  
    IPP 12, 18, 33, 35, 36  
    overview 12, 17  
    SMB 12, 18, 35, 44  
    troubleshooting 51  
    *See also* LPR printing

## Q

queues, print  
    adding 34, 35, 39, 51, 52  
    advantages 14, 17  
    data array 54  
    deleting 43  
    limitations 21  
    logs 48, 49  
    naming 24, 35, 36, 42, 44, 52  
    pausing jobs 40  
    resuming jobs 41  
    settings 41, 42  
    setup 24, 41  
    status checking 40  
    troubleshooting 52  
    *See also* LPR printing

quotas, print 29, 30, 47

## S

SACLs (service access control lists) 21, 22  
security 17, 21, 22, 23  
serial number, server 51  
Server Admin 12, 18, 22, 38  
serveradmin tool  
    logs 49, 50  
    naming queues 43  
    pausing queue 41  
    print job management 45, 46  
    print quotas 48  
    settings 25, 42, 53  
    status checking 38, 40  
    stopping service 38  
service access control lists. *See* SAACLs  
setup procedures. *See* configuration  
shared resources, printers as 12, 14, 39  
sharing name, queue 42, 44  
single sign-on authentication 21  
SMB (Server Message Block) service 12, 18, 35, 44

## T

tail tool 49  
Terminal 12, 19  
troubleshooting 51, 52

## U

UNIX users 36  
users  
    print quotas 29, 30, 47  
    queue settings changes 41, 42  
    troubleshooting printing 51, 52  
    UNIX 36  
    Windows 35, 44, 52  
    Workgroup Manager 12, 18  
    *See also* clients

## W

Windows users  
    queue names 35, 52  
    setup 35, 44  
    troubleshooting printing 52  
    *See also* SMB  
Workgroup Manager 12, 13, 18