



Mac OS X Server Upgrading and Migrating

For Version 10.6 Snow Leopard

© 2009 Apple Inc. All rights reserved.

The owner or authorized user of a valid copy of Mac OS X Server software may reproduce this publication for the purpose of learning to use such software. No part of this publication may be reproduced or transmitted for commercial purposes, such as selling copies of this publication or for providing paid-for support services.

Every effort has been made to make sure that the information in this manual is correct. Apple Inc. is not responsible for printing or clerical errors.

Apple

1 Infinite Loop
Cupertino CA 95014-2084
www.apple.com

The Apple logo is a trademark of Apple Inc., registered in the U.S. and other countries. Use of the "keyboard" Apple logo (Option-Shift-K) for commercial purposes without the prior written consent of Apple may constitute trademark infringement and unfair competition in violation of federal and state laws.

Apple, the Apple logo, iCal, iChat, Snow Leopard, Mac, Macintosh, QuickTime, Safari, Xgrid, Xserve, and WebObjects are trademarks of Apple Inc., registered in the U.S. and other countries. Finder is a trademark of Apple Inc.

Adobe and PostScript are trademarks of Adobe Systems Incorporated.

Intel, Intel Core, and Xeon are trademarks of Intel Corp. in the U.S. and other countries.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

PowerPC™ and the PowerPC logo™ are trademarks of International Business Machines Corporation, used under license therefrom.

UNIX is a registered trademark of The Open Group.

Other company and product names mentioned herein are trademarks of their respective companies. Mention of third-party products is for informational purposes only and constitutes neither an endorsement nor a recommendation. Apple assumes no responsibility with regard to the performance or use of these products.

019-1414/2009-05-29

Contents

5	Preface: About This Guide
5	What's New in Mac OS X Server v10.6
5	What's in This Guide
6	Using Onscreen Help
6	Documentation Map
7	Viewing PDF Guides Onscreen
8	Printing PDF Guides
8	Getting Documentation Updates
9	Getting Additional Information
10	Chapter 1: Before You Begin
10	Servers from Which You Can Upgrade or Migrate
10	Upgrading to v10.6
10	Migrating from a Pre-10.5 Version Server to v10.6
11	Migrating Users and Groups
11	Saving and Reusing User and Group Accounts
11	System Accounts
14	Applying a New Serial Number
15	Chapter 2: Upgrading Mac OS X Server v10.5
15	Understanding What Can Be Reused
16	Upgrading an Open Directory Master and Its Replicas
16	Step-by-Step Instructions
17	Step 1: Update your server to v10.5.6 or later
17	Step 2: Save all service settings
17	Step 3: Save Print server settings
17	Step 4: Perform an upgrade to v10.6
19	Step 5: Make adjustments as needed after initial server setup
22	Upgrading Apache Web Server to v2.2 from v1.3
24	Chapter 3: Migrating from Mac OS X Server v10.5
24	Before You Begin
25	Understanding What You Can Migrate
26	Tools You Can Use

26	Migrating From a Volume
28	Step-by-Step Instructions for Manual Migration
28	Step 1: Export users and groups
29	Step 2: Create archives of the following files
34	Step 3: Note current share points and privileges
34	Step 4: Copy archive files to the new server
34	Step 5: Set up the home directory infrastructure
35	Step 6: Import users and groups and other data
36	Step 7: Relocate the following saved data files
43	Step 8: Set up share points and privileges
43	Step 9: Test the new server
45	Chapter 4: Upgrading Mac OS X Server v10.4
45	Understanding What Can Be Reused
46	Upgrading an Open Directory Master and Its Replicas
47	Step-by-Step Instructions
47	Step 1: Update your server to v10.4.11
47	Step 2: Save all service settings
47	Step 3: Save Print server settings
47	Step 4: Perform an upgrade to v10.6
50	Step 5: Make adjustments as needed after initial server setup
53	Upgrading Apache Web Server to v2.2 from v1.3
54	Chapter 5: Migrating from Mac OS X Server v10.4
54	Before You Begin
55	Understanding What You Can Migrate
56	Tools You Can Use
56	Migrating From a Volume
58	Step-by-Step Instructions for Manual Migration
58	Step 1: Export users and groups
59	Step 2: Create archives of the following files
64	Step 3: Note current share points and privileges
64	Step 4: Copy archive files to the new server
64	Step 5: Set up the home directory infrastructure
65	Step 6: Import users and groups and other data
67	Step 7: Relocate the following saved data files
73	Step 8: Set up share points and privileges
73	Step 9: Test the new server
74	Index

About This Guide

This guide provides instructions for moving to Mac OS X v10.6 from a previous version of the server or migrating data to a Mac OS X Server v10.6.

Upgrading and Migrating contains instructions for reusing data and settings of previous server versions. There are two approaches:

- Perform an upgrade installation. This approach leaves all your data and settings in place and lets you reuse your existing server hardware for Mac OS X Server v10.6. You can perform an upgrade installation of v10.5.6 and v10.4.11 servers.
- Manually migrate data and settings. This approach transfers data and settings to a different computer—one running Mac OS X Server v10.6. You can migrate data and settings from v10.5.6 and v10.4.11 servers.

What's New in Mac OS X Server v10.6

Mac OS X Server v10.6 offers major enhancements in several key areas:

- **WebObjects:** Support for WebObjects is removed with Mac OS X v10.6.

What's in This Guide

This guide includes the following sections:

- Chapter 1, “Before You Begin” summarizes upgrade and migration options and requirements. Read this chapter to understand your options, and then see the chapter relevant to your upgrade or migration scenario.
- Chapter 2, “Upgrading Mac OS X Server v10.5,” describes how to upgrade a v10.5.6 or later server to v10.6.
- Chapter 3, “Migrating from Mac OS X Server v10.5,” describes how to migrate data from a v10.5.6 or later server to a different computer running v10.6.
- Chapter 4, “Upgrading Mac OS X Server v10.4,” describes how to upgrade a v10.4.11 server to v10.6.

- Chapter 5, “Migrating from Mac OS X Server v10.4,” describes how to migrate data from a v10.4.11 server to a different computer running v10.6.

Note: Because Apple periodically releases new versions and updates to its software, images shown in this book may be different from what you see on your screen.

Using Onscreen Help

You can get task instructions onscreen in Help Viewer while you’re managing Mac OS X Server. You can view help on a server, or on an administrator computer. (An administrator computer is a Mac OS X computer with Mac OS X Server administrator software installed on it.)

To get the most recent onscreen help for Mac OS X Server:

- Open Server Admin or Workgroup Manager and then:
 - Use the Help menu to search for a task you want to perform.
 - Choose Help > Server Admin Help or Help > Workgroup Manager Help to browse and search the help topics.

The onscreen help contains instructions taken from *Advanced Server Administration* and other advanced administration guides.


To see the most recent server help topics:

- Make sure the server or administrator computer is connected to the Internet while you’re getting help.

Help Viewer automatically retrieves and caches the most recent server help topics from the Internet. When not connected to the Internet, Help Viewer displays cached help topics.

Documentation Map

Mac OS X Server has a suite of guides that cover management of individual services. Each service may depend on other services for maximum utility. The documentation map below shows some related guides that you may need in order to fully configure Mac OS X Server to your specifications. You can get these guides in PDF format from the Mac OS X Server Resources website at www.apple.com/server/macosx/resources/.



Viewing PDF Guides Onscreen

While reading the PDF version of a guide onscreen:

- Show bookmarks to see the guide's outline, and click a bookmark to jump to the corresponding section.
- Search for a word or phrase to see a list of places where it appears in the guide. Click a listed place to see the page where it occurs.

- Click a cross-reference to jump to the referenced section. Click a web link to visit the website in your browser.

Printing PDF Guides

If you want to print a guide, you can take these steps to save paper and ink:

- Save ink or toner by not printing the cover page.
- Save color ink on a color printer by looking in the panes of the Print dialog for an option to print in grays or black and white.
- Reduce the bulk of the printed document and save paper by printing more than one page per sheet of paper. In the Print dialog, change Scale to 115% (155% for *Getting Started*). Then choose Layout from the untitled pop-up menu. If your printer supports two-sided (duplex) printing, select one of the Two-Sided options. Otherwise, choose 2 from the Pages per Sheet pop-up menu, and optionally choose Single Hairline from the Border menu. (If you're using Mac OS X v10.4 or earlier, the Scale setting is in the Page Setup dialog and the Layout settings are in the Print dialog.)

You may want to enlarge the printed pages even if you don't print double sided, because the PDF page size is smaller than standard printer paper. In the Print dialog or Page Setup dialog, try changing Scale to 115% (155% for *Getting Started*, which has CD-size pages).

Getting Documentation Updates

Periodically, Apple posts revised help pages and new editions of guides. Some revised help pages update the latest editions of the guides.

- To view new onscreen help topics for a server application, make sure your server or administrator computer is connected to the Internet and click "Latest help topics" or "Staying current" in the main help page for the application.
- To download the latest guides in PDF format, go to the Mac OS X Server Resources website at www.apple.com/server/resources/.
- An RSS feed listing the latest updates to Mac OS X Server documentation and onscreen help is available. To view the feed, use an RSS reader application such as Safari or Mail and go to:
`feed://helposx.apple.com/rss/snowleopard/serverdocupdates.xml`

Getting Additional Information

For more information, consult these resources:

- *Read Me documents*—get important updates and special information. Look for them on the server discs.
- *Mac OS X Server website* (www.apple.com/server/macosx/)—enter the gateway to extensive product and technology information.
- *Mac OS X Server Support website* (www.apple.com/support/macosxserver/)—access hundreds of articles from Apple’s support organization.
- *Apple Discussions website* (discussions.apple.com/)—share questions, knowledge, and advice with other administrators.
- *Apple Mailing Lists website* (www.lists.apple.com/)—subscribe to mailing lists so you can communicate with other administrators using email.
- *Apple Training and Certification website* (www.apple.com/training/)—hone your server administration skills with instructor-led or self-paced training, and differentiate yourself with certification.

Before You Begin

1

Take a few moments to become familiar with upgrade and migration options and requirements.

If you're using Mac OS X Server v10.4 or v10.5, you may not need to migrate server data to a different computer. You might be able to *upgrade* your server, a process that installs and sets up Mac OS X Server v10.6 on your existing server computer while preserving data and service settings.

Servers from Which You Can Upgrade or Migrate

You can reuse server data and settings with Mac OS X Server v10.6 by:

- Upgrading server v10.5.6 or later or v10.4.11
- Migrating from versions 10.5.6 or later or 10.4.11

Upgrading to v10.6

You can upgrade your v10.5.6 or later or v10.4.11 server to v10.6 or later if:

- You don't need to reformat the current computer's hard disk.
- Your server hardware has:
 - An Intel
 - At least 1 gigabyte (GB) of random access memory (RAM)
 - At least 20 gigabytes (GB) of disk space available

When you upgrade a server, you perform an upgrade installation from the server installation disc on your server computer. Data and settings are preserved for you, and manual adjustments are minimal.

Migrating from a Pre-10.5 Version Server to v10.6

Even if your existing server meets the minimum requirements for upgrading, you may want to migrate instead of upgrade. For example, you may be updating computers and decide that you want to reestablish your server environment on newer computers.

Migrations from Mac OS X Server versions 10.5.6 or later and 10.4.11 are supported. When you migrate, you install and perform initial setup of Mac OS X Server v10.6 on a computer, restore files onto the v10.6 computer from the pre-v10.6 computer, and make manual adjustments as required.

You'll need to migrate, not upgrade, to Mac OS X Server v10.6 if:

- Your v10.4.11 or v10.5.6 or later server's hard disk needs reformatting.
- Your v10.4.11 or v10.5.6 or later server doesn't have:
 - An Intel
 - At least 1 GB of RAM
 - At least 20 GB of disk space available
- You want to move data and settings you've been using on a v10.4.11 or v10.5.6 or later server to different server hardware.
- The server version you've been using is earlier than v10.4.11.

Migrating Users and Groups

All versions of Mac OS X Server you can migrate from are supported by tools that help you move user and group accounts from an existing server to a v10.6 server.

Note: All existing POP/IMAP accounts are disabled after an upgrade or migration. See the appropriate migration chapter for information about restoring accounts.

Saving and Reusing User and Group Accounts

To save user and group accounts to be imported later, back up the Open Directory master database or export the user and group accounts using Workgroup Manager. To restore user and group accounts, restore the Open Directory master database or use Workgroup Manager or the `dsimport` tool.

Each migration chapter provides instructions for using these tools.

System Accounts

When you install Mac OS X Server, several user and group accounts are created in the local directory. These accounts are sometimes called *system accounts* because they're used by the server system software. For a description of how predefined accounts are used, see *User Management*.

You can't change the names or IDs of system accounts, so when you migrate users and groups, don't try to. However, you can add users during migration to two system groups—admin and wheel:

- The wheel and admin groups allows members to use the `su` (substitute user) command in the Terminal application to log in on a remote computer as the root user. (Members should know the root password to use the `su` command.)

Use `ssh` to log in, enter `su`, then supply the root password when prompted.

- The admin group gives members the right to administer Mac OS X Server. Admin users can use server management applications and install software that requires administrator privileges. By default, members of the admin group can gain root privilege using the `sudo` command.

Here are the predefined user accounts:

Name	Short name	UID
Unprivileged User	nobody	-2
System Administrator	root	0
System Services	daemon	1
Printing Services	lp	26
Postfix User	postfix	27
VPN MPPE Key	vpn_nnnnnnnnnnnn	57
World Wide Web Server	www	70
Apple Events User	eppc	71
MySQL Server	mysql	74
sshd Privilege separation	sshd	75
QuickTime Streaming Server	qtss	76
Cyrus IMAP User	cyrus	77
Mailman User	mailman	78
Application Server	appserver	79
Clamav User	clamav	82
Amavisd User	amavisd	83
Jabber User	jabber	84
Xgrid Controller	xgridcontroller	85
Xgrid Agent	xgridagent	86
Application Owner	appowner	87
WindowServer	windowserver	88
Unknown User	unknown	99

Here are the predefined groups:

Short name	Group ID
nobody	-2
nogroup	-1
wheel	0
daemon	1
kmem	2
sys	3
tty	4
operator	5
mail	6
bin	7
staff	20
lp	26
postfix	27
postdrop	28
utmp	45
uucp	66
dialer	68
network	69
www	70
mysql	74
sshd	75
qtss	76
mailman	78
appserverusr	79
admin	80
appserveradm	81
clamav	82
amavisd	83
jabber	84
xgridcontroller	85
xgridagent	86

Short name	Group ID
appowner	87
windowserver	88
accessibility	90
unknown	99

Applying a New Serial Number

When upgrading to Mac OS X Server v10.6, you must configure your system to use a v10.6 serial number.

Upgrading Mac OS X Server v10.5

2

Use the instructions in this chapter to upgrade a v10.5.6 or later server to v10.6.

You can upgrade computers with Mac OS X Server v10.5.6 or later that don't require hard disk reformatting and that have:

- An Intel processor
- At least 1 GB of RAM
- At least 20 GB of disk space available

Understanding What Can Be Reused

When you upgrade from Mac OS X Server v10.5.6 or later, virtually all existing data and settings remain available for use, but note the following:

- NetBoot images created using Mac OS X Server v10.4 and v10.5 can be reused. NetBoot images created using earlier versions cannot be used.
- When upgrading to Mac OS X Server v10.6, the launch daemons (`/System/Library/LaunchDaemons`) are replaced by the Mac OS X Server v10.6 version of these daemons.
- PHP: Hypertext Preprocessor (PHP) 4 reached its end of life on December 31, 2007 as announced at www.php.net. If you upgrade to Mac OS X Server v10.6 and retain PHP 4.4.x and Apache 1.3, you must switch to PHP 5.x and Apache 2.2 to maintain a secure PHP.
- If you are using Apache v1.3 on Mac OS X Server v10.5, you should perform an upgrade from Apache v1.3 to Apache v2.2 prior to upgrading to Mac OS X Server v10.6. When you upgrade to Mac OS X Server v10.6, a clean default configuration of Apache v2.2 is used for Web service and any Apache v1.3 configuration files are preserved in the `/etc/httpd/` folder. For more information about upgrading from Apache v1.3 to Apache v2.2, see "Upgrading Apache Web Server to v2.2 from v1.3" on page 22

Upgrading an Open Directory Master and Its Replicas

When the server you want to upgrade is an Open Directory master or replica, upgrade the master and then upgrade the replicas.

To upgrade the master and its replicas:

- 1 Upgrade the master to v10.6 using the instructions in “Step-by-Step Instructions” on page 47.

While you’re upgrading the master, client computers can’t connect to it for Open Directory services.

Clients may experience a delay while automatically finding an Open Directory replica server. In addition, you can eliminate this delay by changing the DHCP service to use the address of an Open Directory replica server if the server provides clients with an LDAP server address.

When the master upgrade is complete, you can change the DHCP service to use the address of the master. For instructions on configuring LDAP settings in DHCP service, see *Network Services Administration*.

- 2 Upgrade each replica server to v10.6.
- 3 Using Server Admin, connect to each replica server and reconnect the replicas with the master.


For information about resetting passwords in the master, see “Directory Services” on page 51.

Step-by-Step Instructions

To upgrade a v10.5.6 or later server to v10.6, follow the instructions in this section.

- 1 Update your server to v10.5.6.

- 2 Perform an upgrade to v10.6.



- 3 Make adjustments as needed after initial server setup.

Step 1: Update your server to v10.5.6 or later

If necessary, use Software Update to update your server to v10.5.6 or later.

Step 2: Save all service settings

Use `serveradmin` or Server Admin to export all service settings for reference. Also, use System Profiler to generate a full profile of your system. Store the exported service settings and your server's profile on a removable drive or another system.

Important: Before upgrading you should also create a full, bootable, tested-by-booting clone of your server as a backup in case you need it in the future.

Step 3: Save Print server settings

Use the `serveradmin settings print` command to save the print server settings before you start the upgrade.

```
serveradmin settings print > exported_print_settings
```

Also, record the names and IDs of the CUPS queues for later use.

Step 4: Perform an upgrade to v10.6

You can use the v10.6 installation disc to perform the upgrade locally on your server computer if it has a display, keyboard, and optical drive attached.

After the upgrade is complete, the computer restarts and Server Assistant leads you through initial server setup. Your existing settings are displayed, and you can change them if you like.

To upgrade to v10.6 and perform initial server setup locally:

- 1 Make sure that DHCP or DNS servers your server depends on are running.
- 2 Turn on the computer and insert the installation disc into the optical drive.
- 3 Restart the server while holding down the C key on the keyboard.

The computer boots from the installation disc. You can release the C key when you see the Apple logo.

For information about restarting a headless Xserve system, see the user's guide that came with the system.

- 4 When the Installer opens, follow the onscreen instructions to proceed through each pane, then click Continue.

Note: In the Select a Destination pane, be sure to select the disk or partition on which v10.5.6 or later is installed.

During installation, progress information is displayed.

After installation is complete, the computer restarts and Server Assistant opens so you can perform initial server setup.

- 5 Move through the Assistant's panes, following the onscreen instructions.
- 6 In the Serial Number pane you must enter a unique server software serial number for each server you upgrade.

You'll find the number printed on the materials provided with the server software package. If you have a site license, a registered owner name and organization must be entered exactly as specified by your Apple representative.

- 7 To initiate setup of the server, click Setup.
- 8 When server setup is complete, log in.

Note: You may need to manually enable and start Mail server after upgrading the server.

To upgrade to v10.6 and perform initial server setup remotely:

- 1 Make sure that DHCP or DNS servers your server depends on are running.
- 2 Start the computer from the installation disc.

The procedure you use depends on whether the target server has an optical drive that can read your installation disc. If you have an installation DVD, the optical drive must be able to read DVD discs.

If the target server has a keyboard and an optical drive that can read your installation disc, insert the installation disc into the optical drive, then hold down the C key on the keyboard while restarting the computer.

If the target server is an Xserve system with a built-in optical drive that can read your installation disc, start the server using the installation disc by following the instructions in *Xserve User's Guide* for starting from a system disc.

If the target server lacks a built-in optical drive that can read your installation disc, you can start it in target disk mode and insert the installation disc into the optical drive on your administrator computer. You can also use an external FireWire optical drive.

If the target server is an Xserve system, you can move its drive module to another Xserve system that has an optical drive capable of reading your installation disc.

Instructions for using target disk mode and external optical drives are in the *Quick Start* guide, *Getting Started* guide, or user's guide that came with your Xserve system or Macintosh computer.

- 3 On an administrator computer, open Server Assistant by opening Server Admin and choosing "Installing Remote Server" from the Server menu. You don't need to be an administrator on the local computer to use Server Assistant.
- 4 In the Destination, identify the server you want to upgrade by entering the IP address of the server in the IP Address field.
- 5 Enter the first eight characters of the computer's hardware serial number (case-sensitive) and click Continue.

- 6 Proceed by following the onscreen instructions.
- 7 When the Volumes pane appears, select a target disk or volume (partition) and click Install.
During installation, progress information is displayed.
- 8 When the message appears explaining that a earlier version of Mac OS X is installed on the volume you have chosen, select Upgrade.
After installation is complete, the computer restarts, and then Server Assistant opens and displays a Welcome pane.
- 9 To initiate server setup, select “Set up Mac OS X Server remotely” and click Continue.
- 10 In the Servers pane, click Add.
- 11 From the Address pop-up menu chose the server you’re upgrading.
- 12 Enter the root password that was used by the previous version of Mac OS X in the Password field and click Continue to connect to the server.
- 13 Select the server you want to upgrade from the list and click Continue.
- 14 Move through the Assistant’s panes, following the onscreen instructions.
- 15 In the Serial Number pane, you must enter a unique server software serial number for each server you upgrade.
You’ll find the number printed on the materials provided with the server software package. If you have a site license, enter the registered owner name and organization exactly as specified by your Apple representative.
- 16 Click Setup.
- 17 To initiate setup of the server, click Apply.
- 18 When server setup is complete, close Server Assistant.

Note: You may need to manually enable and start Mail server after upgrading the server.

Step 5: **Make adjustments as needed after initial server setup**

Now you can use Workgroup Manager, Server Admin, Terminal, and other applications to refine your server’s settings and take advantage of new v10.6 features.

For an explanation of new and changed features, see the administration guide for individual services. Following are a few suggestions of particular interest.

Print Server Settings

To restore Print server settings, you must first recreate the original CUPS queues before importing the saved settings.

For printers connected directly to the server via USB, the queues are created by CUPS when the printers are plugged in and turned on. However, for network printers, you must add the printers using either Server Admin > Print (for LPR or AppleTalk printers) or System Preferences > Print & Fax (for all printer types).

Important: When recreating a CUPS queue, make sure you give it the same name as the one it had before the upgrading process. If the name is not the same, Server Admin won't import the settings correctly.

Important: When creating the print queues using the Print & Fax pane of System Preferences, specify Generic Postscript (Generic PPD) for any queue that enforces quotas because there are known issues with third-party printer drivers and CUPS quotas. For more information about this issue, see the Knowledge Base article at <http://docs.info.apple.com/article.html?artnum=303538>.

After creating the print queues, import the saved settings:

```
serveradmin settings exported_print_settings
```

WebObjects

Mac OS X Server v10.6 does not support WebObjects. After the upgrade to Mac OS X Server v10.6, your WebObjects applications are placed in the /Library/WebObjects/ folder and your WebObjects frameworks are placed in the /Library/Frameworks/ folder.

Secure Sockets Layer (SSL) Certificates

Use Server Admin to import existing SSL certificates you want to continue to use for iChat, Open Directory, Mail, or Web services.

To import an SSL certificate:

- 1 Open Server Admin.
- 2 Select the upgraded server in the list of computers and services.
- 3 Click Certificates.
- 4 Import the certificates you want to use.

You can also create a self-signed certificate and generate a Certificate Signing Request (CSR) to obtain an SSL certificate from a certificate authority and then install the certificate.

- 5 Click Save.
- 6 Activate the certificates per service.

For more information about importing, creating, and activating self-signed certificates, see *iChat Server Administration*, *Mail Server Administration*, *Open Directory Administration*, and *Web Technologies Administration*.

Groups

If you want groups to use new v10.6 features such as nesting and stricter membership checking, upgrade group records using Workgroup Manager.

To upgrade a group record:

- 1 Open Workgroup Manager.
- 2 Open the directory that contains the groups of interest.
- 3 Select one or more groups and click “Upgrade legacy group.”
- 4 Click Save.

Directory Services

If you want to enable Kerberos for an Open Directory master that it’s not enabled for, use the following command, which maintains existing passwords and adds them to a new KDC:

```
slapconfig -kerberize
```

If you have user accounts with crypt passwords and you don’t Kerberize them using the above command, you can use Workgroup Manager to upgrade to Open Directory passwords.

To use Workgroup Manager, open the application and access the directory where the user account resides. Authenticate as domain administrator, then select a user with a crypt password. Click Advanced, choose Open Directory from the User Password Type pop-up menu, click Basic, specify a new password, and click Save.

For more information about `slapconfig`, see its man page.

LDAP ACLs

Due to a change in format, you must manually move the LDAP access control lists (ACLs) after the upgrade is finished. During the upgrade process, the container or record for accesscontrols and ACL information is made available as Read-Only.

Add custom ACLs to the new `olcAccess` attribute (in `olcBDBConfig`). You must also use the `set` directive instead of the `group` directive.

DNS

When you select DNS in Server Admin for the first time after an upgrade, Server Admin prompts you whether to upgrade.

If you click Don’t Upgrade, Server Admin leaves the DNS configuration files as they were before the v10.6 upgrade. DNS still runs, but you can’t make DNS configuration changes using Server Admin. If you need to make changes, you must edit the DNS configuration files.

If you click Upgrade, Server Admin upgrades the configuration files to the v10.6 format. After that, you can use Server Admin to make DNS configuration changes.

NetBoot Images

You can reuse NetBoot images created using versions 10.4 and 10.5 following the upgrade.

To manage Netboot images, you use System Image Utility, which replaces Network Image Utility during the upgrade.

The Open Directory Upgrade Log

Information about upgrading the Open Directory LDAP server is stored in `/Library/Logs/slapconfig.log`.

Web Service

If you've modified `/etc/httpd/workers.properties`, reapply your changes to the version of the file that's installed with Mac OS X Server v10.6. The 10.6 version `workers.properties` file has a new entry for Blog service.

Upgrading Apache Web Server to v2.2 from v1.3

When you upgrade from Mac OS X Server v10.5.6 or later to Mac OS X Server v10.6, the upgrade process configures Web service with a clean default configuration of Apache v2.2 and preserves Apache v1.3 configuration files for reference in `/etc/httpd/` folder.

To configure Apache v2.2 after upgrading to Mac OS X Server v10.6, with the preserved configuration settings of Apache v1.3, use the `transApache.rb` script. This script automates the Apache v1.3 to Apache v2.2 translation. When the script is complete, use either Server Admin or a text editor to customize the Apache v2.2 configuration.

To upgrade to Apache v2.2:

- 1 Open Terminal.
- 2 Type the following command:

```
$ sudo /usr/sbin/translateApache.rb
```

The `translateApache.rb` script outputs the `/Library/Logs/Migration/webconfigmigrator.log` log file that can be used for manual tweaking of the generated Apache v2.2 files.

Note: Apache v2.2 runs as a 64-bit process on appropriate hardware.

WARNING: There are possible side-effects when running of the Apache 1-to-Apache 2 conversion script, particularly for security-related settings, which will impact the security of your upgrade. Use Server Admin or a text editor to customize the Apache v2.2 configuration settings.

For more information about upgrading to Apache v2.2, see *Web Technologies Administration*.

Migrating from Mac OS X Server v10.5

Use the instructions in this chapter when you need to migrate data from a v10.5.6 or later server to a different computer running v10.6.

You can migrate data from Mac OS X Server v10.5.6 or later computers that can't or won't be upgraded to v10.6 or later. Such computers may:

- Require hard disk reformatting or replacement with a newer computer.
- Be using server hardware that doesn't have:
 - An Intel processor
 - At least 1 GB of RAM
 - At least 20 GB of available disk space

Before You Begin

Before using the instructions in this chapter, perform initial setup of the v10.6 server that you'll migrate data to. For instructions, see *Getting Started*.

If necessary, upgrade the server whose data you'll migrate so it's running v10.5.6 or later.

When the server is an Open Directory master or replica, set up the v10.6 master and then set up the v10.6 replicas.

To reestablish the master and its replicas:

- 1 Set up the v10.6 master.

While you're setting up the master, client computers can't connect to the v10.5.6 or later master for Open Directory services.

In addition, clients may experience a delay while automatically finding the nearest Open Directory replica server. You can eliminate this delay by changing the DHCP service to use the address of an Open Directory replica server if it provides clients with an LDAP server address.

When the v10.6 master is ready, you can change the DHCP service to use the address of the master.

For instructions on configuring LDAP settings in DHCP service, see *Network Services Administration*.

- 2 Change the v10.5.6 or later replica's role to standalone, then set up the v10.6 server to be a replica of the v10.6 master.

For instructions about changing a server's Open Directory role to standalone and replica, see *Open Directory Administration*.

For information about resetting passwords in the master, see Step "Directory Services" on page 21.

Understanding What You Can Migrate

The information in "Step-by-Step Instructions for Manual Migration" on page 58 describes how to reuse the following v10.5 data with v10.6:

- Web configuration data
- Web content
- MySQL data
- Mail database
- WebMail data
- FTP configuration files
- LDAP server settings
- NetBoot images
- Tomcat data
- AFP settings
- SMB Settings
- IP firewall configuration
- DNS settings
- DHCP settings
- NAT settings
- Print settings
- VPN settings
- User data, including home directories
- QuickTime Streaming Server files and folders
- QTSS Publisher files and folders
- User and group accounts

- iChat server settings
- Shared Contacts

Use `serveradmin` or Server Admin to export all service settings for reference. Store the exported service settings on a removable drive or another system.

Note: One way to save service settings in Server Admin is to select the service from the list of computers and services on the left, click Settings, and drag the button on the bottom-right to the Desktop. Dragging this button creates a file on the Desktop containing the service settings.

Tools You Can Use

Several tools are available:

- You can use Workgroup Manager to export v10.5 user and group accounts to a delimited file and then import them into a v10.6 server. You can also import users and groups using the command-line `dsimport` tool.
- Workgroup Manager's import facility and the `dsimport` tool also let you import other kinds of data, such as computers and computer lists.
- Use the `59_webconfigmigrator` tool to migrate Web server settings.
- Use the `50_ipfwconfigmigrator` to export Firewall service settings.
- Use the `58_jabbermigrator.pl` to migrate iChat server settings.

Instructions in the following sections explain when and how to use these utilities.

Migrating From a Volume

Mac OS X Server v10.6 supports the migration of data and settings from a volume. You can migrate all of your data, supported services and settings from an volume to your Mac OS X v10.6 Server. When you migrate using a volume the process is automated and doesn't require you to interact. You can migrate from a volume that has Mac OS X Server v10.5.6 installed and configured on it or a volume with a Time Machine backup. The volume can either be installed on the local server or connected using Target Disk Mode.

To migrate to v10.6 from a volume:

- 1 Make sure that the volume you are migrating from is connected through Target Disk Mode or installed locally on your server.
- 2 Turn on the computer and insert the installation disc into the optical drive.
- 3 Restart the server while holding down the C key on the keyboard.

The computer boots from the installation disc. You can release the C key when you see the Apple logo.

For information about restarting a headless Xserve system, see the user's guide that came with the system.

- 4 When the Installer opens, follow the onscreen instructions to proceed through each pane, then click Continue.

During installation, progress information is displayed.

After installation is complete, the computer restarts and Server Assistant opens so you can perform initial server setup.

- 5 Move through the Assistant's panes, following the onscreen instructions.

- 6 In the Serial Number pane you must enter a unique server software serial number.

You'll find the number printed on the materials provided with the server software package. If you have a site license, a registered owner name and organization must be entered exactly as specified by your Apple representative.

- 7 In the Transfer an Existing Server pane, select "Transfer the information from an existing server" and click Continue.

- 8 In the Transfer Your Server pane, select the volume you want to migrate data from and click Transfer.

Note: You may need to manually enable and start Mail server after upgrading the server.

- 9 Continue through the Assistant's panes, following the onscreen instructions.

When the migration is complete the Assistant will proceed through the setting up your server with the migrated data. If your previous version of Mac OS X Server had services that are not supported by Mac OS X Server v10.6 or if any services did not start, an upgrading services message will appear at the end of the setup process.


Important: The Mac OS X Server migration tool does not support the migration of the mail service. If you were using mail service on your previous version of Mac OS X Server, you must migrate the service manually. For more information about manually migrating mail service, see "Step-by-Step Instructions for Manual Migration" and "Step 7: Relocate the following saved data files."

- 10 When the setup is complete, click Proceed.

You will need to log into your newly migrated server and verify the settings of your migrated services.

Step-by-Step Instructions for Manual Migration

To move data from a Mac OS X Server v10.5.6 or later computer to a computer with Mac OS X Server v10.6 installed, follow the instructions in this section.



Step 1: Export users and groups

Use Workgroup Manager to export user and group accounts from an LDAPv3 directory into a character-delimited file that you can import into a directory for use with Mac OS X Server v10.6.

To export users and groups:

- 1 In Workgroup Manager, click Accounts, then click the globe icon below the toolbar and choose the directory that you want to export accounts from.
- 2 Click the lock to authenticate as domain administrator (typically diradmin).
- 3 Click the Users button to export users or click the Groups button to export groups.
- 4 Export user or group accounts as follows:
 - To export all accounts, select all of them.
 - To export one account, select it.
 - To export multiple accounts, select them while holding down the Command or Shift key.
- 5 Choose Server > Export.
- 6 Specify a name to assign to the export file and the location where you want it created.
- 7 Click Export.

When you export users using Workgroup Manager, password information isn't exported. If you want to set passwords, you can modify the export file before you import it or you can individually set passwords after importing using the `passwd` command or Workgroup Manager. For more information about setting passwords after importing users, see *User Management*.

Step 2: Create archives of the following files

Save all data files that you want to reuse with Mac OS X Server v10.6. In "Step 4: Copy archive files to the new server" on page 64 you'll move the files described below, as well as the export file created in "Step 1: Export users and groups" on page 58, to the v10.6 computer.

For large amounts of data, you may want to create one or more tar archives or use `/usr/bin/mkdmg` to create disk image files. You can transfer disk images and tar files using AFP or FTP.

Note: You can also use `scp -r` for secure copying of files and `rsync` for remote file copying. The `rsync` command is particularly useful where you have a large amount of data that can be migrated before cutting over, and then updated in a small downtime window.

To create a tar archive, use the `tar` command in the Terminal application. The command's `-c` flag creates an archive file in tar format. Use the `-f` flag to specify the archive file name. Use the `-v` (verbose) flag to view progress information as the command executes:

```
tar -cvf /MyHFSVolume/Stuff.tar /MyHFSVolume/My\ Stuff
```

The escape character (\ in the example above) indicates a space in the name. You can also use quotation marks to handle embedded spaces:

```
tar -cvf /MyHFSVolume/Stuff.tar "/MyHFSVolume/My Stuff"
```

Web Configuration Data

Save the following files and directories:

- /etc/apache2/httpd.conf
- /etc/apache2/httpd_macosxserver.conf
- /etc/apache2/httpd_mailman.conf
- /etc/apache2/httpd_squirrelmail.conf
- /etc/apache2/magic
- /etc/apache2/mime.types
- /etc/apache2/mime_macosxserver.types
- /etc/apache2/ssl.crt
- /etc/apache2/ssl.key
- /etc/apache2/tomcat.conf
- /Library/WebServer/

Web Content

Copy web content you want to reuse from:

- /Library/WebServer/Documents/
- /Library/WebServer/CGI-Executables/
- Any other location where it resides

MySQL Data

Mac OS X Server v10.5.6 and v10.6 use MySQL v5.0.67.

To migrate MySQL databases from one computer to another, you can use the `mysqldump` command to back up your data. This command has several forms depending on the scope of data to be backed up: individual tables, single databases, or the entire set of databases on the server.

To back up individual tables, enter:

```
mysqldump database tb1 [tb2 tb3...] > backup-file.sql
```

where *database* is the name of the database containing the listed tables and *tb1*, *tb2*, and *tb3* represent table names.

To back up one or more databases, enter:

```
mysqldump --databases db1 [db2 db3...] > backup-file.sql
```

To back up all database on the system, enter:

```
mysqldump --all-databases > backup-file.sql
```

Additional instructions for database backup and restore can be found in the MySQL documentation at www.mysql.org.

To back up tables or databases that require root access (for example, grant tables or other restricted data), run `mysqldump` with the `--user=root` and `-p` options:

```
mysqldump --user=root -p --all-databases > backup-file.sql
```

The `-p` option causes `mysqldump` to prompt for the MySQL root password before proceeding.

Mail Database

If you want to reuse the Mail server database and store, stop Mail server if it's running and save the mail files. When Mail server is not running, you can copy all Mail server directories.

By default:

- The mail database resides in `/var/imap/`.
- The mail store resides in `/var/spool/imap/`. You can back up individual mail storage folders or the entire mail store.

The `ditto` command-line tool is useful for backing up mail files. For more information about `ditto`, see its man page.

Also, save a copy of the file `/usr/bin/cyrus/bin/ctl_mboxlist` so you can move it to the v10.6 server in “Step 4: Copy archive files to the new server” on page 64. You need this file to migrate the mail database successfully in “Step 7: Relocate the following saved data files” on page 67.

Webmail Data

If you've been using SquirrelMail that was installed when you installed v10.5 and you want to continue using it after migration, make copies of the address books and preferences stored in `/var/db/squirrelmail/data/`.

FTP Configuration Files

To migrate your FTP settings, save these configuration files:

In this directory	Save these files
/Library/FTPService/Configuration/	ftpassess ftpconversions ftphosts ftpgroups ftpusers
/Library/FTPService/Messages/	banner.txt welcome.txt limit.txt

LDAP Server

Back up the LDAP server configuration information.

To back up the Open Directory database, which includes LDAP server configuration:

- 1 In Server Admin, select Open Directory from the list of computers and services.
- 2 Click Archive.
- 3 In the “Archive in” field, browse for the archive path.
- 4 Click the Archive button.
- 5 In the Archive Name field, enter the name of the file where the information will be stored.
- 6 In the Password field, enter the password for the archive.
- 7 Click OK.

AFP

Save /Library/Preferences/com.apple.AppleFileServer.plist.

SMB

Copy /etc/smb.conf to /etc/smb.conf.old.

NetBoot Images

You can migrate NetBoot images created using Mac OS X Server v10.5.

Save the <name>.nbi folder for each image you want to migrate, noting the path to the folder if you want to recreate it in v10.6.

Also save the NetBoot settings. In Server Admin, select NetBoot from the list of computers and services on the left, click Settings, and drag the button on the bottom-right to the Desktop. Dragging this button creates a file on the Desktop containing the NetBoot service settings. Save this file.

WebObjects and Frameworks

Mac OS X Server v10.6 does not support WebObjects. You can still save your WebObjects applications and frameworks located in:

- /Library/WebObjects/
- /System/Library/WebObjects/

Tomcat Data

Save any Tomcat servlets you want to reuse. They're in /Library/Tomcat/webapps/.

If you've installed Axis independent of the version supplied with your server, save any Simple Object Access Protocol (SOAP) services.

IP Firewall

In the Terminal application, run this command:

```
sudo /System/Library/ServerSetup/MigrationExtras/50_ipfwconfigmigrator
```

Then, save the contents of /etc/ipfilter.

NAT

Save the contents of /etc/nat/natd.plist.

Print

Use the `serveradmin settings print` command to save print settings before you start the migration process.

```
serveradmin settings print > exported_print_settings
```

Also, record the names and IDs of the CUPS queues for later use.

VPN

Copy:

- /Library/Preferences/SystemConfiguration/com.apple.RemoteAccessServers.plist
- /Library/Keychains/System.keychain
- /etc/racoon/psk.text

If L2TP is set up and psk.text stores the IPsec shared secret, the shared secret may also be stored in com.apple.RemoteAccessServers.plist or System.keychain.

DNS

Save the file /etc/named.conf and the directory /var/named/ and all its contents.

DHCP

In Server Admin, select DHCP from the list of computers and services on the left, click Settings, and drag the button on the bottom-right to the Desktop.

Dragging this button creates a file on the Desktop containing the DHCP service settings.

Save this file.

User Data

Save any user data files or folders you want to reuse, especially home directory folders.

QuickTime Streaming Server Files and Folders

Save files and folders in `/Library/QuickTimeStreaming/`.

QTSS Publisher Files and Folders

Save the following:

- The files and folders in `/Library/Application Support/Apple/QTSS Publisher/`
- The files and folders in each QTSS Publisher user's path:
`/Users/<publisher_user>/Library/Application Support/Apple/QTSS Publisher`

iChat Server

Save the following folders:

- `/var/jabber/spool`
- `/etc/jabber`

Step 3: Note current share points and privileges

If your v10.5 server has share points and privileges you want to recreate on the v10.6 server, make a note of them. Record which share points are for home directories.

Step 4: Copy archive files to the new server

Transfer the files you saved in "Step 1: Export users and groups" on page 58 and "Step 2: Create archives of the following files" on page 59 to the v10.6 server.

To transfer tar files or disk images using FTP:

- 1 Use Server Admin on the new server to start FTP service.
- 2 Set up sharing for a folder where you'll place files you transfer from the v10.5 computer.
- 3 From the v10.5 server, use FTP service to copy the tar files or disk images to the v10.6 computer.
- 4 On the v10.6 server, double-click a tar file to extract its contents or double-click a disk image to mount it.

Step 5: Set up the home directory infrastructure

Set up the destination for home directories you want to restore.

The home directory location identified in imported user accounts must match the physical location of the restored home directories, including the share point location.

For details on how to perform the steps in the following procedure, see *User Management*.

To prepare the server to store home directories:

- 1 Create the folder you want to serve as the home directory share point, if required. You can use the predefined /Users folder, if you like.
- 2 Open Server Admin on the server where you want home directories to reside.
- 3 Click File Sharing to set up a share point for home directories.

If user accounts will reside in a shared Open Directory directory, create a dynamically automounted AFP or NFS share point for the home directories. Make sure the share point is published in the directory where the user accounts that depend on it will reside.

- 4 In Workgroup Manager on the computer where you'll import users, click Accounts, then open the directory where you'll import users.

If you restore home directories in locations that won't exactly match the locations identified in exported user records, you can define a preset that identifies the restore location. If you identify the preset when you import users, the new location will replace the existing location in user records.

You can also use the preset to specify other default settings you want imported users to inherit, such as password settings, mail settings, and so forth.

Step 6: Import users and groups and other data

If you're migrating users and groups from an Open Directory master, use the instructions in "LDAP Server Settings" on page 69. If you're migrating local node users and groups, use Workgroup Manager or the `dsimport` tool.

For more information about importing by using Workgroup Manager, see *User Management*.

For more information about `dsimport` and a description of Workgroup Manager export format, see *User Management*.

To import users and groups using Workgroup Manager:

- 1 Place the export files you created in Step "Step-by-Step Instructions for Manual Migration" on page 58 in a location accessible from your server.

You can modify user accounts in an export file if you want to set passwords before importing users. For instructions, see *User Management*.

Additionally, you can set up the preset you defined in Step "Step 5: Set up the home directory infrastructure" on page 64 above so that user passwords are validated using Open Directory authentication, and you can set up the password validation options so users must change their passwords the next time they log in.

For information about using Kerberos passwords, see the last step in this sequence.

- 2 In Workgroup Manager, click the Accounts button.
- 3 Click the globe icon in the toolbar to open the directory where you want to import accounts.
- 4 Click the lock to authenticate as domain administrator.
- 5 Choose Server > Import, select the import file, and specify import options.
If you're using a preset, make sure you specify the preset.
- 6 Click Import.
- 7 If you want groups to use new v10.6 features, upgrade groups using Workgroup Manager.

In Workgroup Manager, open the directory containing the groups, select one or more of the groups, click "Upgrade legacy group," and click Save.

- 8 To create home directories for imported users, use one of the following options.

Create home directories one at a time by selecting a user account in Workgroup Manager, clicking Home, then clicking Create Home Now.

Create all home directories by using the `-a` argument of the `createhomedir` command. For details, see *User Management* or the man page for `createhomedir`.

A home directory associated with an AFP share point is created the first time a user logs in, if it doesn't exist already.

- 9 If you want to enable Kerberos for an Open Directory master that it's not enabled for, use the following command, which maintains existing passwords and adds them to a new KDC.

```
slapconfig -kerberize
```

If you have user accounts with crypt passwords and you don't Kerberize them using the above command, you can use Workgroup Manager to upgrade to Open Directory passwords.

To use Workgroup Manager, open the application and access the directory where the user account resides. Authenticate as the Open Directory administrator (typically `diradmin`), then select a user with a crypt password. Click Advanced, choose Open Directory from the User Password Type pop-up menu, click Basic, specify a new password, and click Save.

For more information about `slapconfig`, see its man page.

Step 7: Relocate the following saved data files

Place the files you saved from your v10.5 server in their final locations.

Web Configuration Data

To migrate the web configuration:

- 1 Open Server Admin.
- 2 Under the v10.6 server in the list of computers and services, click Web.
- 3 Click Stop Web if Web service is running.
- 4 Delete the following files:
 - /etc/apache2/ssl.crt
 - /etc/apape2/ssl.key
- 5 Delete only the content in the /etc/apache2/sites/ folder.
- 6 Copy the saved v10.5 files and directory onto the v10.6 server.
- 7 In the Terminal application, enter the following command:

```
cd /etc/apache2
```
- 8 As the root user, open the httpd.conf file for editing.
- 9 In the httpd.conf file:
 - Replace `var/run/proxy` with `/var/run/proxy-1.3`.
 - Replace `/var/run/httpd.pid` with `/var/run/http-1.3.pid`.
- 10 Save your changes.
- 11 To migrate the web settings, in Terminal, run the following command:

```
sudo /System/Library/ServerSetup/translateApache.rb
```
- 12 If you've modified /etc/apache2/workers.properties, reapply all your changes to the version of the file that's installed with server v10.6.

The v10.6 workers.properties file has a new entry for Blog service.
- 13 In Server Admin, start Web service.

Web Content

Copy saved web content to the following locations and anywhere else you have placed web content on the server:

- /Library/WebServer/Documents/
- /Library/WebServer/CGI-Executables/

MySQL Data

Before importing backed up MySQL data, make sure that the MySQL service is active. You can activate the MySQL service using Server Admin or the `serveradmin` command.

To activate the MySQL service using the `serveradmin` command, enter:

```
serveradmin start mysql
```

To import database backups enter:

```
mysql < backup-file.sql
```

To import data into databases that require privileged access, run `mysql` with the `--user=root` and `-p` options:

```
mysql --user=root -p < backup-file.sql
```

The `-p` option causes `mysql` to prompt for the MySQL root password before proceeding.

When running MySQL and PHP on the same server, you may find that PHP cannot connect to MySQL or that authentication errors occur when using PHP. For more information and workarounds, see the following AppleCare KnowledgeBase articles:

- “Mac OS X Server v10.5: PHP and MySQL authentication issues” (article 301456)”
- “Mac OS X Server v10.5: Issues connecting PHP to MySQL” (article 301457)”

Additional instructions for MySQL database backup and restoration can be found in the MySQL documentation at www.mysql.org.

Mail Database

To migrate the mail database:

- 1 Make sure that v10.5 Mail server isn’t running.

Open Server Admin, then click Mail. If the Mail circle on the left side is not grayed out, click Stop Mail at the lower left.

- 2 Restore the saved mail database and mail store.

By default the mail database resides in `/var/imap/` and the mail store in `/var/spool/imap/`.

- 3 Make sure the mail directories and their contents are owned by the `_cyrus` user and mail group.

- 4 In Server Admin, select Mail from the list of computers and services.

- 5 Click Settings, click Advanced, and click Database to indicate where you restored the database and mail store.

- 6 Click Save.

- 7 Run the mail database `61_migrate_cyrus_db` script:

```
sudo /System/Library/ServerSetup/MigrationExtras/61_migrate_cyrus_db
```

- 8 Run the following command to ensure that the index files for all mail accounts are in good working order:

```
sudo /usr/bin/cyrus/bin/reconstruct -i
```

- 9 In Server Admin, start Mail server by clicking Mail, then click Start Mail.

Webmail Data

Place saved address books and preferences in `/var/db/squirrelmail/data/`.

FTP Configuration Files

Copy saved FTP configuration files to:

- /Library/FTPService/Configuration/
- /Library/FTPService/Messages/

LDAP Server Settings

Restore the LDAP server configuration information.

To restore the Open Directory database, which includes LDAP server configuration:

- 1 In Server Admin, select Open Directory from the list of computers and services:
- 2 Click Archive.
- 3 In the “Archive from” field, browse for the archive.
- 4 Click the Restore button.
- 5 In the Password field, enter the password for the archive.
- 6 Click OK.

AFP Configuration

To migrate the AFP configuration, restore /Library/Preferences/com.apple.AppleFileServer.plist.

SMB Configuration

To migrate the SMB configuration, copy /etc/smb.conf.old to the new server, and run the following script:

```
sudo /System/Library/ServerSetup/MigrationExtras/70_smbconfigmigrator
```

This script generates the settings in /Library/Preferences/SystemConfiguration/com.apple.smb.server.plist for the v10.5 server using the settings from /etc/smb.conf.old.

NetBoot Images

Copy the <name>.nbi folder for each image you want to migrate, optionally placing it into the location where it previously resided.

Also, restore the NetBoot settings file.

To restore the NetBoot settings:

- 1 Open Server Admin and select NetBoot from the list of computers and services.
- 2 Choose Server > Import > Service Settings to import the NetBoot settings from the file you exported earlier (see “NetBoot Images” on page 62).
- 3 Review the NetBoot settings to make sure they were imported correctly.

Tomcat Data

Restore Tomcat servlets to /Library/Tomcat/webapps/.

Place SOAP services you want to migrate in `/Library/Tomcat/webapps/axis/`.
Mac OS X Server v10.6 includes a version of Axis that may be newer or older than the version you've been using.

IP Firewall Configuration

To migrate the IP firewall configuration, restore the `/etc/ipfilter` folder.

Open Server Admin and click Firewall to inspect the settings and make sure they are correct.

NAT

Restore the contents of `/etc/nat/natd.plist`.

You can restore the v10.6 default settings for NAT (stored in `/etc/natd/natd.plist.default`) at any time by deleting the active configuration file (`/etc/nat/natd.plist`). The next time NAT is accessed using Server Admin, the default configuration file is used to recreate the active configuration file.

Note: In v10.6, the default setting of `unregistered_only` in `/etc/nat/natd.plist.default` is true.

Print Server Settings

To restore Print server settings, you must first recreate the original CUPS queues before importing the saved settings.

In the case of printers connected directly to the server via USB, the queues are created by CUPS when the printers are plugged in and turned on. However, for network printers, you must add the printers using Server Admin > Print (for LPR or AppleTalk printers) or System Preferences > Print & Fax (for all printer types).

Important: When recreating a CUPS queue, make sure you give it the same name as the one it had on the older system. If the name is not the same, Server Admin won't import the settings correctly.

Important: When creating the print queues using the Print & Fax pane of System Preferences, specify Generic Postscript (Generic PPD) for any queue that enforces quotas because there are known issues with third-party printer drivers and CUPS quotas. For more information about this issue, see the Knowledge Base article at <http://docs.info.apple.com/article.html?artnum=303538>.

After creating the print queues, import the saved settings:

```
serveradmin settings exported_print_settings
```

VPN

Restore the following:

- `/Library/Preferences/SystemConfiguration/com.apple.RemoteAccessServers.plist`.

- /Library/Keychains/System.keychain
- /etc/racoon/psk.text

If L2TP is set up and psk.text stores the IPsec shared secret, the shared secret may also be stored in com.apple.RemoteAccessServers.plist or System.keychain.

Migrate the VPN MPPE Key user by using the `vpnaddkeyagentuser` command-line tool. For more information about this command, see its man page.

DNS Configuration

To migrate the DNS configuration:

- 1 Restore the file /etc/named.conf and the directory /var/named/ and all its contents.
- 2 In Server Admin, select DNS from the list of computers and services.

A dialog box appears prompting you whether to upgrade:

- If you click Don't Upgrade, Server Admin leaves the DNS configuration files as they were before the v10.6 migration. DNS will still run, but you can't make DNS configuration changes using Server Admin. To make changes, you must directly edit the DNS configuration files.
- If you click Upgrade, Server Admin upgrades the configuration files to the v10.6 format. After that, you can use Server Admin to make DNS configuration changes.

DHCP Settings

To migrate the DHCP configuration:

- 1 Open Server Admin and select DHCP from the list of computers and services.
- 2 Choose Server > Import > Service Settings to import DHCP settings from the file you exported earlier (see "DHCP" on page 63).
- 3 Inspect the Subnets and Static Maps panes of the DHCP service to make sure the subnet and static binding settings have been imported correctly.

User Data

Restore saved user data files.

Place home directories in locations that match the locations in the imported user records. If necessary, you can use Workgroup Manager to edit user accounts so the locations in the account and on disk are the same.

QuickTime Streaming Server Files and Folders

Follow instructions in *QuickTime Streaming and Broadcasting Administration* to reuse files and folders saved from /Library/QuickTimeStreaming/.

QTSS Publisher Files and Folders

QTSS Publisher has been removed from Mac OS X Server v10.6. However, files created using the QTSS Publisher should continue to work on v10.6.

Restore QTSS Publisher files and folders on Mac OS X Server v10.6.

QTSS Publisher Media and MP3 files should be stored in:

- /Library/Application Support/Apple/ QTSS Publisher/Libraries/
- /Users/<publisher_user>/Library/Application Support/Apple/QTSS Publisher/Libraries/

To migrate QTSS Publisher media and MP3 playlists to QTSS Web Admin:

- 1 Move all folders in /Library/Application Support/Apple/QTSS Publisher/Playlists/ to /Library/QuickTimeStreaming/Playlists.

For example, you would move:

/Library/Application Support/Apple/QTSS Publisher/Playlists/my_playlist/

to

/Library/QuickTimeStreaming/Playlists/my_playlist/

- 2 Verify that the owner of folders and files in /Library/QuickTimeStreaming/Playlists is qtss.
- 3 For media playlists, verify that the folder /Library/Application Support/Apple/QTSS Publisher/Libraries/Media/ contains the media files listed in the .playlist files.
- 4 For MP3 playlists, verify that the folder /Library/Application Support/Apple/QTSS Publisher/Libraries/MP3/ contains the media files listed in the .playlist files.
- 5 For every playlist, update its .config file so that paths point to the new playlist folder in /Library/QuickTimeStreaming/Playlists.

This includes the paths defined in the pid_file, playlist_file, and sdp_file (media playlists only) preferences.

- 6 Enable QTSS web-based administration using Server Admin.
- 7 Open Web Admin using Safari (<http://<hostname>:1220>) and log in.
- 8 Click Playlists.

You can now start manage QTSS Publisher playlists using QTSS Web Admin.

For information about using Web Admin, see the *QuickTime Streaming Server Darwin Streaming Server Administrator's Guide* available at developer.apple.com/opensource/server/streaming.

iChat Server

To migrate iChat server settings:

- 1 Restore the following folders:
 - /var/jabber/spool
 - /etc/jabber
- 2 Run the following script with root privileges:

```
sudo "/System/Library/ServerSetup/MigrationExtras/  
58_jabbermigrator.pl
```

The `58_jabbermigrator.pl` script invokes three other scripts to migrate the iChat server settings. If needed, you can run these scripts individually to customize the migration. The scripts are documented and contain helpful information.

Shared Contacts

If you were using Shared Contacts in Mac OS X Server Version 10.5, you can upgrade these to use Address Book Server in Mac OS X Server Version 10.6.

To migrate Shared Contact:

- 1 Run the following command:

```
/usr/sbin/ContactsMigrator -s /LDAPv3/yourserverName -d http://  
yourserverName:8800/addressbooks/groups/mygroup/addressbook/ -u  
username -p password
```

Where:

- `yourserverName` is the fully qualified domain name of your Open Directory server where the Shared Contacts are located
- `username` is the username of an administrator for the Address Book Server
- `password` is the password of the administrator username you entered

For information about `ContactsMigrator`, see its man page. For the basics of command-line tool usage, see *Introduction to Command-Line Administration*.

Step 8: Set up share points and privileges

Recreate the share points and privileges as required.

To create a share point and set privileges:

- 1 Open Server Admin and click File Sharing.
- 2 Click Volumes and select the volume or folder you want to share.
- 3 Click Share.
- 4 Click Permissions to set up access privileges.
- 5 Click Save.

New share points are shared using AFP, SMB, and FTP, but not NFS. To export a share point using NFS, use the Protocol pane. For more information about setting up share points, see *File Server Administration*.

Step 9: Test the new server

To test the new server:

- 1 Open Workgroup Manager and inspect user and group accounts.

- 2 Open Server Admin and inspect settings for services whose configuration data you migrated.

Upgrading Mac OS X Server v10.4

4

Use the instructions in this chapter to upgrade a v10.4.11 server to v10.6.

You can upgrade computers with Mac OS X Server v10.4.11 that don't require hard disk reformatting and that have:

- An Intel processor
- At least 1 GB of RAM
- At least 20 GB of disk space available

Understanding What Can Be Reused

When you upgrade from Mac OS X Server v10.4.11, virtually all existing data and settings remain available for use, but note the following:

- NetBoot images created using Mac OS X Server v10.3 and v10.4 can be reused. NetBoot images created using earlier versions cannot be used.
- When upgrading to Mac OS X Server v10.6, the launch daemons (`/System/Library/LaunchDaemons`) are replaced by the Mac OS X Server v10.6 version of these daemons.
- Upgrading to v10.6 removes the QTSS Publisher application but leaves the files used by the application. These files should continue to work on v10.6, but you must move them to the appropriate locations. For more information about moving them, see "QTSS Publisher Files and Folders" on page 64.
- PHP: Hypertext Preprocessor (PHP) 4 will reach its end of life on December 31, 2007 and critical security fixes will not be made after August 8, 2008, as announced at www.php.net. If you upgrade to Mac OS X Server v10.6 and retain PHP 4.4.x and Apache v1.3, plan on switching to PHP 5.x and Apache v2.2 before August 8, 2008 to maintain a secure PHP.

- When you upgrade to Mac OS X Server v10.6, a clean default configuration of Apache v2.2 is used for Web service and any Apache v1.3 configuration files are preserved in the `/etc/httpd/` folder. For more information about upgrading from Apache v1.3 to Apache v2.2, see “Upgrading Apache Web Server to v2.2 from v1.3” on page 53

Note: Macintosh Manager is not supported in Mac OS X Server v10.6.

Upgrading an Open Directory Master and Its Replicas

When the server you want to upgrade is an Open Directory master or replica, upgrade the master and then upgrade the replicas.

To upgrade the master and its replicas:

- 1 Upgrade the master to v10.6 using the instructions in “Step-by-Step Instructions” on page 47.

While you’re upgrading the master, client computers can’t connect to it for Open Directory services.

Clients may experience a delay while automatically finding an Open Directory replica server. In addition, you can eliminate this delay by changing the DHCP service to use the address of an Open Directory replica server if the server provides clients with an LDAP server address.

When the master upgrade is complete, you can change the DHCP service to use the address of the master. For instructions on configuring LDAP settings in DHCP service, see *Network Services Administration*.

- 2 Upgrade each replica server to v10.6.
- 3 Using Server Admin, connect to each replica server and reconnect the replicas with the master.


For information about resetting passwords in the master, see “Directory Services” on page 51.

Step-by-Step Instructions

To upgrade a v10.4.11 server to v10.6, follow the instructions in this section.

1 Update your server to v10.4.11.

2 Perform an upgrade to v10.6.



3 Make adjustments as needed after initial server setup.

Step 1: Update your server to v10.4.11

If necessary, use Software Update to update your server to v10.4.11.

Step 2: Save all service settings

Use `serveradmin` or Server Admin to export all service settings for reference. Also, use System Profiler to generate a full profile of your system. Store the exported service settings and your server's profile on a removable drive or another system.

Important: Before upgrading you should also create a full, bootable, tested-by-booting clone of your server as a backup in case you need it in the future.

Step 3: Save Print server settings

Use the `serveradmin settings print` command to save the print server settings before you start the upgrade.

```
serveradmin settings print > exported_print_settings
```

Also, record the names and IDs of the CUPS queues for later use.

Step 4: Perform an upgrade to v10.6

You can use the v10.6 installation disc to perform the upgrade locally on your server computer if it has a display, keyboard, and optical drive attached.

After the upgrade is complete, the computer restarts and Server Assistant leads you through initial server setup. Your existing settings are displayed, and you can change them if you like.

To upgrade to v10.6 and perform initial server setup locally:

- 1 Make sure that DHCP or DNS servers your server depends on are running.
- 2 Turn on the computer and insert the installation disc into the optical drive.
- 3 Restart the server while holding down the C key on the keyboard.

The computer boots from the installation disc. You can release the C key when you see the Apple logo.

For information about restarting a headless Xserve system, see the user's guide that came with the system.

- 4 When the Installer opens, follow the onscreen instructions to proceed through each pane, then click Continue.

Note: In the Select a Destination pane, be sure to select the disk or partition on which v10.4.11 or later is installed.

During installation, progress information is displayed.

After installation is complete, the computer restarts and Server Assistant opens so you can perform initial server setup.

- 5 Move through the Assistant's panes, following the onscreen instructions.
- 6 In the Serial Number pane you must enter a unique server software serial number for each server you upgrade.

You'll find the number printed on the materials provided with the server software package. If you have a site license, a registered owner name and organization must be entered exactly as specified by your Apple representative.

- 7 To initiate setup of the server, click Setup.
- 8 When server setup is complete, log in.

Note: You may need to manually enable and start Mail server after upgrading the server.

To upgrade to v10.6 and perform initial server setup remotely:

- 1 Make sure that DHCP or DNS servers your server depends on are running.
- 2 Start the computer from the installation disc.

The procedure you use depends on whether the target server has an optical drive that can read your installation disc. If you have an installation DVD, the optical drive must be able to read DVD discs.

If the target server has a keyboard and an optical drive that can read your installation disc, insert the installation disc into the optical drive, then hold down the C key on the keyboard while restarting the computer.

If the target server is an Xserve system with a built-in optical drive that can read your installation disc, start the server using the installation disc by following the instructions in *Xserve User's Guide* for starting from a system disc.

If the target server lacks a built-in optical drive that can read your installation disc, you can start it in target disk mode and insert the installation disc into the optical drive on your administrator computer. You can also use an external FireWire optical drive.

If the target server is an Xserve system, you can move its drive module to another Xserve system that has an optical drive capable of reading your installation disc.

Instructions for using target disk mode and external optical drives are in the *Quick Start* guide, *Getting Started* guide, or user's guide that came with your Xserve system or Macintosh computer.

- 3 On an administrator computer, open Server Assistant by opening Server Admin and choosing "Installing Remote Server" from the Server menu. You don't need to be an administrator on the local computer to use Server Assistant.
- 4 In the Destination, Identify the server you want to upgrade by entering the IP address of the server in the IP Address field.
- 5 Enter the first eight characters of the computers hardware serial number (case-sensitive) and click Continue.
- 6 Proceed by following the onscreen instructions.
- 7 When the Volumes pane appears, select a target disk or volume (partition) and click Install.

During installation, progress information is displayed.

- 8 When the message appears explaining that a earlier version of Mac OS X is installed on the volume you have chosen, select Upgrade.

After installation is complete, the computer restarts, and then Server Assistant opens and displays a Welcome pane.

- 9 To initiate server setup, select "Set up Mac OS X Server remotely" and click Continue.
- 10 In the Servers pane, click Add.
- 11 From the Address pop-up menu chose the server you're upgrading.
- 12 Enter the root password that was used by the previous version of Mac OS X in the Password field and click Continue to connect to the server.
- 13 Select the server you want to upgrade from the list and click Continue.
- 14 Move through the Assistant's panes, following the onscreen instructions.
- 15 In the Serial Number pane, you must enter a unique server software serial number for each server you upgrade.

You'll find the number printed on the materials provided with the server software package. If you have a site license, enter the registered owner name and organization exactly as specified by your Apple representative.

- 16 Click Setup.
- 17 To initiate setup of the server, click Apply.
- 18 When server setup is complete, close Server Assistant.

Note: You may need to manually enable and start Mail server after upgrading the server.

Step 5: Make adjustments as needed after initial server setup

Now you can use Workgroup Manager, Server Admin, Terminal, and other applications to refine your server's settings and take advantage of new v10.6 features.

For an explanation of new and changed features, see the administration guide for individual services. Following are a few suggestions of particular interest.

Print Server Settings

To restore Print server settings, you must first recreate the original CUPS queues before importing the saved settings.

For printers connected directly to the server via USB, the queues are created by CUPS when the printers are plugged in and turned on. However, for network printers, you must add the printers using either Server Admin > Print (for LPR or AppleTalk printers) or System Preferences > Print & Fax (for all printer types).

Important: When recreating a CUPS queue, make sure you give it the same name as the one it had before the upgrading process. If the name is not the same, Server Admin won't import the settings correctly.

Important: When creating the print queues using the Print & Fax pane of System Preferences, specify Generic Postscript (Generic PPD) for any queue that enforces quotas because there are known issues with third-party printer drivers and CUPS quotas. For more information about this issue, see the Knowledge Base article at <http://docs.info.apple.com/article.html?artnum=303538>.

After creating the print queues, import the saved settings:

```
serveradmin settings exported_print_settings
```

WebObjects

Mac OS X Server v10.6 does not support WebObjects. After the upgrade to Mac OS X Server v10.6, your WebObjects applications are placed in the /Library/WebObjects/ folder and your WebObjects frameworks are placed in the /Library/Frameworks/ folder.

Secure Sockets Layer (SSL) Certificates

Use Server Admin to import existing SSL certificates you want to continue to use for iChat, Open Directory, Mail, or Web services.

To import an SSL certificate:

- 1 Open Server Admin.
- 2 Select the upgraded server in the list of computers and services.
- 3 Click Certificates.
- 4 Import the certificates you want to use.

You can also create a self-signed certificate and generate a Certificate Signing Request (CSR) to obtain an SSL certificate from a certificate authority and then install the certificate.

- 5 Click Save.
- 6 Activate the certificates per service.

For more information about importing, creating, and activating self-signed certificates, see *iChat Server Administration*, *Mail Server Administration*, *Open Directory Administration*, and *Web Technologies Administration*.

Groups

If you want groups to use new v10.6 features such as nesting and stricter membership checking, upgrade group records using Workgroup Manager.

To upgrade a group record:

- 1 Open Workgroup Manager.
- 2 Open the directory that contains the groups of interest.
- 3 Select one or more groups and click “Upgrade legacy group.”
- 4 Click Save.

Directory Services

After upgrading, you may want to convert a shared NetInfo directory to LDAP. For information about the advantages of using LDAP and how to use Server Admin to conduct the conversion, see *Open Directory Administration*.

If you want to enable Kerberos for an Open Directory master that it’s not enabled for, use the following command, which maintains existing passwords and adds them to a new KDC:

```
slapconfig -kerberize
```

If you have user accounts with crypt passwords and you don’t Kerberize them using the above command, you can use Workgroup Manager to upgrade to Open Directory passwords.

To use Workgroup Manager, open the application and access the directory where the user account resides. Authenticate as domain administrator, then select a user with a crypt password. Click Advanced, choose Open Directory from the User Password Type pop-up menu, click Basic, specify a new password, and click Save.

For more information about `slapconfig`, see its man page.

LDAP ACLs

Due to a change in format, you must manually move the LDAP access control lists (ACLs) after the upgrade is finished. During the upgrade process, the container or record for accesscontrols and ACL information is made available as Read-Only.

Add custom ACLs to the new `olcAccess` attribute (in `olcBDBConfig`). You must also use the `set` directive instead of the `group` directive.

DNS

When you select DNS in Server Admin for the first time after an upgrade, Server Admin prompts you whether to upgrade.

If you click Don't Upgrade, Server Admin leaves the DNS configuration files as they were before the v10.6 upgrade. DNS still runs, but you can't make DNS configuration changes using Server Admin. If you need to make changes, you must edit the DNS configuration files.

If you click Upgrade, Server Admin upgrades the configuration files to the v10.6 format. After that, you can use Server Admin to make DNS configuration changes.

NetBoot Images

You can reuse NetBoot images created using versions 10.3 and 10.4 following the upgrade.

To manage Netboot images, you use System Image Utility, which replaces Network Image Utility during the upgrade.

The Open Directory Upgrade Log

Information about upgrading the Open Directory LDAP server is stored in `/Library/Logs/slapconfig.log`.

Web Service

If you've modified `/etc/httpd/workers.properties`, reapply your changes to the version of the file that's installed with Mac OS X Server v10.6. The 10.6 version `workers.properties` file has a new entry for Blog service.

Upgrading Apache Web Server to v2.2 from v1.3

When you upgrade from Mac OS X Server v10.4.11 to Mac OS X Server v10.6, the upgrade process configures Web service with a clean default configuration of Apache v2.2 and preserves Apache v1.3 configuration files for reference in `/etc/httpd/` folder.

To configure Apache v2.2 after upgrading to Mac OS X Server v10.6, with the preserved configuration settings of Apache v1.3, use the `transApache.rb` script. This script automates the Apache v1.3 to Apache v2.2 translation. When the script is complete, use either Server Admin or a text editor to customize the Apache v2.2 configuration.

To upgrade to Apache v2.2:

- 1 Open Terminal.
- 2 Type the following command:

```
$ sudo /usr/sbin/translateApache.rb
```

The `translateApache.rb` script outputs the `/Library/Logs/Migration/webconfigmigrator.log` file that can be used for manual tweaking of the generated Apache v2.2 files

Note: Apache v2.2 runs as a 64-bit process on appropriate hardware.

WARNING: There are possible side-effects when running of the Apache 1-to-Apache 2 conversion script, particularly for security-related settings, which will impact the security of your upgrade. Use Server Admin or a text editor to customize the Apache v2.2 configuration settings.

For more information about upgrading to Apache v2.2, see *Web Technologies Administration*.

Migrating from Mac OS X Server v10.4

5

Use the instructions in this chapter when you need to migrate data from a v10.4.11 server to a different computer running v10.6.

You can migrate data from Mac OS X Server v10.4.11 computers that can't or won't be upgraded to v10.6 or later. Such computers may:

- Require hard disk reformatting or replacement with a newer computer.
- Be using server hardware that doesn't have:
 - An Intel processor
 - At least 1 GB of RAM
 - At least 20 GB of available disk space

Before You Begin

Before using the instructions in this chapter, perform initial setup of the v10.6 server that you'll migrate data to. For instructions, see *Getting Started*.

If necessary, upgrade the server whose data you'll migrate so it's running v10.4.11.

When the server is an Open Directory master or replica, set up the v10.6 master and then set up the v10.6 replicas.

To reestablish the master and its replicas:

- 1 Set up the v10.6 master.

While you're setting up the master, client computers can't connect to the v10.4.11 master for Open Directory services.

In addition, clients may experience a delay while automatically finding the nearest Open Directory replica server. You can eliminate this delay by changing the DHCP service to use the address of an Open Directory replica server if it provides clients with an LDAP server address.

When the v10.6 master is ready, you can change the DHCP service to use the address of the master.

For instructions on configuring LDAP settings in DHCP service, see *Network Services Administration*.

- 2 Change the v10.4.11 replica's role to standalone, then set up the v10.6 server to be a replica of the v10.6 master.

For instructions about changing a server's Open Directory role to standalone and replica, see *Open Directory Administration*.

For information about resetting passwords in the master, see Step "Directory Services" on page 51.

Understanding What You Can Migrate

The information in "Step-by-Step Instructions for Manual Migration" on page 58 describes how to reuse the following v10.4 data with v10.6:

- Web configuration data
- Web content
- MySQL data
- Mail database
- WebMail data
- FTP configuration files
- LDAP server settings
- NetBoot images
- Tomcat data
- JBoss applications
- AFP settings
- SMB Settings
- IP firewall configuration
- DNS settings
- DHCP settings
- NAT settings
- Print settings
- VPN settings
- User data, including home directories
- QuickTime Streaming Server files and folders
- QTSS Publisher files and folders

- User and group accounts
- iChat server settings

Use `serveradmin` or Server Admin to export all service settings for reference. Store the exported service settings on a removable drive or another system.

Note: One way to save service settings in Server Admin is to select the service from the list of computers and services on the left, click Settings, and drag the button on the bottom-right to the Desktop. Dragging this button creates a file on the Desktop containing the service settings.

In v10.6, `watchdog` has been replaced by `launchd`. To reenable automatic hardware restart, use the Energy Saver pane of System Preferences. To migrate settings for services you added to `/etc/watchdog.conf`, create a `launchd` plist file and install it into `/System/Library/LaunchDaemons/`. For more information about `launchd`, see its man page.

Tools You Can Use

Several tools are available:

- You can use Workgroup Manager to export v10.4 user and group accounts to a delimited file and then import them into a v10.6 server. You can also import users and groups using the command-line `dsimport` tool.
- Workgroup Manager's import facility and the `dsimport` tool also let you import other kinds of data, such as computers and computer lists.
- Use the `59_webconfigmigrator` tool to migrate Web service settings.
- Use the `50_ipfwconfigmigrator` to export Firewall service settings.
- Use the `58_jabbermigrator.pl` to migrate iChat service settings.

Instructions in the following sections explain when and how to use these utilities.

Migrating From a Volume

Mac OS X Server v10.6 supports the migration of data and settings from a volume. You can migrate all of your data, supported services and settings from an volume to your Mac OS X v10.6 Server. When you migrate using a volume the process is automated and doesn't require you to interact. You can migrate from a volume that has Mac OS X Server v10.4.11 installed and configured on it or a volume with a Time Machine backup. The volume can either be installed on the local server or connected using Target Disk Mode.

To migrate to v10.6 from a volume:

- 1 Make sure that the volume you are migrating from is connected through Target Disk Mode or installed locally on your server.

- 2 Turn on the computer and insert the installation disc into the optical drive.
- 3 Restart the server while holding down the C key on the keyboard.

The computer boots from the installation disc. You can release the C key when you see the Apple logo.

For information about restarting a headless Xserve system, see the user's guide that came with the system.
- 4 When the Installer opens, follow the onscreen instructions to proceed through each pane, then click Continue.

During installation, progress information is displayed.

After installation is complete, the computer restarts and Server Assistant opens so you can perform initial server setup.
- 5 Move through the Assistant's panes, following the onscreen instructions.
- 6 In the Serial Number pane you must enter a unique server software serial number.

You'll find the number printed on the materials provided with the server software package. If you have a site license, a registered owner name and organization must be entered exactly as specified by your Apple representative.
- 7 In the Transfer an Existing Server pane, select "Transfer the information from an existing server" and click Continue.
- 8 In the Transfer Your Server pane, select the volume you want to migrate data from and click Transfer.

Note: You may need to manually enable and start Mail server after upgrading the server.
- 9 Continue through the Assistant's panes, following the onscreen instructions.


When the migration is complete the Assistant will proceed through the setting up your server with the migrated data. If your previous version of Mac OS X Server had services that are not supported by Mac OS X Server v10.6 or if any services did not start, an upgrading services message will appear at the end of the setup process.

Important: The Mac OS X Server migration tool does not support the migration of the mail service. If you were using mail service on your previous version of Mac OS X Server, you must migrate the service manually. For more information about manually migrating mail service, see "Step-by-Step Instructions for Manual Migration" and "Step 7: Relocate the following saved data files."
- 10 When the setup is complete, click Proceed.

You will need to log into your newly migrated server and verify the settings of your migrated services.

Step-by-Step Instructions for Manual Migration

To move data from a Mac OS X Server v10.4.11 computer to a computer with Mac OS X Server v10.6 installed, follow the instructions in this section.



Step 1: Export users and groups

Use Workgroup Manager to export user and group accounts from a NetInfo or LDAPv3 directory into a character-delimited file that you can import into a directory for use with Mac OS X Server v10.6.

To export users and groups:

- 1 In Workgroup Manager, click Accounts, then click the globe icon below the toolbar and choose the directory that you want to export accounts from.
- 2 Click the lock to authenticate as domain administrator (typically diradmin).
- 3 Click the Users button to export users or click the Groups button to export groups.
- 4 Export user or group accounts as follows:
 - To export all accounts, select all of them.
 - To export one account, select it.
 - To export multiple accounts, select them while holding down the Command or Shift key.
- 5 Choose Server > Export.
- 6 Specify a name to assign to the export file and the location where you want it created.
- 7 Click Export.

When you export users using Workgroup Manager, password information isn't exported. If you want to set passwords, you can modify the export file before you import it or you can individually set passwords after importing using the `passwd` command or Workgroup Manager. For more information about setting passwords after importing users, see *User Management*.

Step 2: Create archives of the following files

Save all data files that you want to reuse with Mac OS X Server v10.6. In "Step 4: Copy archive files to the new server" on page 64 you'll move the files described below, as well as the export file created in "Step 1: Export users and groups" on page 58, to the v10.6 computer.

For large amounts of data, you may want to create one or more tar archives or use `/usr/bin/mkdmg` to create disk image files. You can transfer disk images and tar files using AFP or FTP.

Note: You can also use `scp -r` for secure copying of files and `rsync` for remote file copying. The `rsync` command is particularly useful where you have a large amount of data that can be migrated before cutting over, and then updated in a small downtime window.

To create a tar archive, use the `tar` command in the Terminal application. The command's `-c` flag creates an archive file in tar format. Use the `-f` flag to specify the archive file name. Use the `-v` (verbose) flag to view progress information as the command executes:

```
tar -cvf /MyHFSVolume/Stuff.tar /MyHFSVolume/My\ Stuff
```

The escape character (\ in the example above) indicates a space in the name. You can also use quotation marks to handle embedded spaces:

```
tar -cvf /MyHFSVolume/Stuff.tar "/MyHFSVolume/My Stuff"
```

Web Configuration Data

Save the following files and directories:

- /etc/httpd/httpd.conf
- /etc/httpd/httpd_macosxserver.conf
- /etc/httpd/httpd_mailman.conf
- /etc/httpd/httpd_squirrelmail.conf
- /etc/httpd/magic
- /etc/httpd/mime.types
- /etc/httpd/mime_macosxserver.types
- /etc/httpd/ssl.crt
- /etc/httpd/ssl.key
- /etc/httpd/tomcat.conf
- /etc/webperfcache/webperfcache.conf
- /Library/WebServer/

Web Content

Copy web content you want to reuse from:

- /Library/WebServer/Documents/
- /Library/WebServer/CGI-Executables/
- Any other location where it resides

MySQL Data

Mac OS X Server v10.4.11 includes MySQL v4.1.22. Mac OS X Server v10.6 installs MySQL v5.0.67.

To migrate MySQL databases from one computer to another, you can use the `mysqldump` command to back up your data. This command has several forms depending on the scope of data to be backed up: individual tables, single databases, or the entire set of databases on the server.

To back up individual tables, enter:

```
mysqldump database tb1 [tb2 tb3...] > backup-file.sql
```

where *database* is the name of the database containing the listed tables and *tb1*, *tb2*, and *tb3* represent table names.

To back up one or more databases, enter:

```
mysqldump --databases db1 [db2 db3...] > backup-file.sql
```

To back up all database on the system, enter:

```
mysqldump --all-databases > backup-file.sql
```

Additional instructions for database backup and restore can be found in the MySQL documentation at www.mysql.org.

To back up tables or databases that require root access (for example, grant tables or other restricted data), run `mysqldump` with the `--user=root` and `-p` options:

```
mysqldump --user=root -p --all-datagases > backup-file.sql
```

The `-p` option causes `mysqldump` to prompt for the MySQL root password before proceeding.

Mail Database

If you want to reuse the Mail server database and store, stop Mail server if it's running and save the mail files. When Mail server is not running, you can copy all Mail server directories.

By default:

- The mail database resides in `/var/imap/`.
- The mail store resides in `/var/spool/imap/`. You can back up individual mail storage folders or the entire mail store.

The `ditto` command-line tool is useful for backing up mail files. For more information about `ditto`, see its man page.

Also, save a copy of the file `/usr/bin/cyrus/bin/ctl_mboxlist` so you can move it to the v10.6 server in “Step 4: Copy archive files to the new server” on page 64. You need this file to migrate the mail database successfully in “Step 7: Relocate the following saved data files” on page 67.

Webmail Data

If you've been using SquirrelMail that was installed when you installed v10.4 and you want to continue using it after migration, make copies of the address books and preferences stored in `/var/db/squirrelmail/data/`.

FTP Configuration Files

To migrate your FTP settings, save these configuration files:

In this directory	Save these files
/Library/FTPService/Configuration/	ftpassess ftpconversions ftphosts ftpgroups ftpusers
/Library/FTPService/Messages/	banner.txt welcome.txt limit.txt

LDAP Server

Back up the LDAP server configuration information.

To back up the Open Directory database, which includes LDAP server configuration:

- 1 In Server Admin, select Open Directory from the list of computers and services.
- 2 Click Archive.
- 3 In the “Archive in” field, browse for the archive path.
- 4 Click the Archive button.
- 5 In the Archive Name field, enter the name of the file where the information will be stored.
- 6 In the Password field, enter the password for the archive.
- 7 Click OK.

AFP

Save /Library/Preferences/com.apple.AppleFileServer.plist.

SMB

Copy /etc/smb.conf to /etc/smb.conf.old.

NetBoot Images

You can migrate NetBoot images created using Mac OS X Server v10.4.

Save the <name>.nbi folder for each image you want to migrate, noting the path to the folder if you want to recreate it in v10.6.

Also save the NetBoot settings. In Server Admin, select NetBoot from the list of computers and services on the left, click Settings, and drag the button on the bottom-right to the Desktop. Dragging this button creates a file on the Desktop containing the NetBoot service settings. Save this file.

WebObjects Applications and Frameworks

Mac OS X Server v10.6 does not support WebObjects. You can still save your WebObjects applications and frameworks located in:

- /Library/WebObjects/
- /System/Library/WebObjects/

Tomcat Data

Save any Tomcat servlets you want to reuse. They're in /Library/Tomcat/webapps/.

If you've installed Axis independent of the version supplied with your server, save any Simple Object Access Protocol (SOAP) services.

JBoss Applications

Save JBoss applications located in /Library/JBoss/3.2/deploy/.

IP Firewall

In the Terminal application, run this command:

```
sudo /System/Library/ServerSetup/MigrationExtras/50_ipfwconfigmigrator
```

Then, save the contents of /etc/ipfilter.

NAT

Save the contents of /etc/nat/natd.plist.

Print

Use the `serveradmin settings print` command to save print settings before you start the migration process.

```
serveradmin settings print > exported_print_settings
```

Also, record the names and IDs of the CUPS queues for later use.

VPN

Copy:

- /Library/Preferences/SystemConfiguration/com.apple.RemoteAccessServers.plist
- /Library/Keychains/System.keychain
- /etc/racoon/psk.text

If L2TP is set up and psk.text stores the IPsec shared secret, the shared secret may also be stored in com.apple.RemoteAccessServers.plist or System.keychain.

DNS

Save the file /etc/named.conf and the directory /var/named/ and all its contents.

DHCP

In Server Admin, select DHCP from the list of computers and services on the left, click Settings, and drag the button on the bottom-right to the Desktop.

Dragging this button creates a file on the Desktop containing the DHCP service settings.

Save this file.

User Data

Save any user data files or folders you want to reuse, especially home directory folders.

QuickTime Streaming Server Files and Folders

Save files and folders in `/Library/QuickTimeStreaming/`.

QTSS Publisher Files and Folders

Save the following:

- The files and folders in `/Library/Application Support/Apple/QTSS Publisher/`
- The files and folders in each QTSS Publisher user's path:
`/Users/<publisher_user>/Library/Application Support/Apple/QTSS Publisher`

iChat Server

Save the following folders:

- `/var/jabber/spool`
- `/etc/jabber`

Step 3: Note current share points and privileges

If your v10.4 server has share points and privileges you want to recreate on the v10.6 server, make a note of them. Record which share points are for home directories.

Step 4: Copy archive files to the new server

Transfer the files you saved in "Step 1: Export users and groups" on page 58 and "Step 2: Create archives of the following files" on page 59 to the v10.6 server.

To transfer tar files or disk images using FTP:

- 1 Use Server Admin on the new server to start FTP service.
- 2 Set up sharing for a folder where you'll place files you transfer from the v10.4 computer.
- 3 From the v10.4 server, use FTP service to copy the tar files or disk images to the v10.6 computer.
- 4 On the v10.6 server, double-click a tar file to extract its contents or double-click a disk image to mount it.

Step 5: Set up the home directory infrastructure

Set up the destination for home directories you want to restore.

The home directory location identified in imported user accounts must match the physical location of the restored home directories, including the share point location.

For details on how to perform the steps in the following procedure, see *User Management*.

To prepare the server to store home directories:

- 1 Create the folder you want to serve as the home directory share point, if required. You can use the predefined /Users folder, if you like.
- 2 Open Server Admin on the server where you want home directories to reside.
- 3 Click File Sharing to set up a share point for home directories.

If user accounts will reside in a shared Open Directory directory, create a dynamically automounted AFP or NFS share point for the home directories. Make sure the share point is published in the directory where the user accounts that depend on it will reside.

- 4 In Workgroup Manager on the computer where you'll import users, click Accounts, then open the directory where you'll import users.

If you restore home directories in locations that won't exactly match the locations identified in exported user records, you can define a preset that identifies the restore location. If you identify the preset when you import users, the new location will replace the existing location in user records.

You can also use the preset to specify other default settings you want imported users to inherit, such as password settings, mail settings, and so forth.

Step 6: Import users and groups and other data

If you're migrating users and groups from an Open Directory master, use the instructions in "LDAP Server Settings" on page 69. If you're migrating local node users and groups, use Workgroup Manager or the `dsimport` tool.

For more information about importing by using Workgroup Manager, see *User Management*.

For more information about `dsimport` and a description of Workgroup Manager export format, see *User Management*.

To import users and groups using Workgroup Manager:

- 1 Place the export files you created in Step "Step-by-Step Instructions for Manual Migration" on page 58 in a location accessible from your server.

You can modify user accounts in an export file if you want to set passwords before importing users. For instructions, see *User Management*.

Additionally, you can set up the preset you defined in Step “Step 5: Set up the home directory infrastructure” on page 64 above so that user passwords are validated using Open Directory authentication, and you can set up the password validation options so users must change their passwords the next time they log in.

For information about using Kerberos passwords, see the last step in this sequence.

- 2 In Workgroup Manager, click the Accounts button.
- 3 Click the globe icon in the toolbar to open the directory where you want to import accounts.
- 4 Click the lock to authenticate as domain administrator.
- 5 Choose Server > Import, select the import file, and specify import options.

If you’re using a preset, make sure you specify the preset.

- 6 Click Import.
- 7 If you want groups to use new v10.6 features, upgrade groups using Workgroup Manager.

In Workgroup Manager, open the directory containing the groups, select one or more of the groups, click “Upgrade legacy group,” and click Save.

- 8 To create home directories for imported users, use one of the following options.

Create home directories one at a time by selecting a user account in Workgroup Manager, clicking Home, then clicking Create Home Now.

Create all home directories by using the `-a` argument of the `createhomedir` command. For details, see *User Management* or the man page for `createhomedir`.

A home directory associated with an AFP share point is created the first time a user logs in, if it doesn’t exist already.

- 9 If you want to enable Kerberos for an Open Directory master that it’s not enabled for, use the following command, which maintains existing passwords and adds them to a new KDC.

```
slapconfig -kerberize
```

If you have user accounts with crypt passwords and you don’t Kerberize them using the above command, you can use Workgroup Manager to upgrade to Open Directory passwords.

To use Workgroup Manager, open the application and access the directory where the user account resides. Authenticate as the Open Directory administrator (typically `diradmin`), then select a user with a crypt password. Click Advanced, choose Open Directory from the User Password Type pop-up menu, click Basic, specify a new password, and click Save.

For more information about `slapconfig`, see its man page.

Step 7: Relocate the following saved data files

Place the files you saved from your v10.4 server in their final locations.

Web Configuration Data

To migrate the web configuration:

- 1 Open Server Admin.
- 2 Under the v10.6 server in the list of computers and services, click Web.
- 3 Click Stop Web if Web service is running.
- 4 Delete the following files:
 - /etc/httpd/ssl.crt
 - /etc/httpd/ssl.key
- 5 Delete only the content in the /etc/httpd/sites/ folder.
- 6 Copy the saved v10.4 files and directory onto the v10.6 server.
- 7 In the Terminal application, enter the following command:

```
cd /etc/httpd
```
- 8 As the root user, open the httpd.conf file for editing.
- 9 In the httpd.conf file:
 - Replace `var/run/proxy` with `/var/run/proxy-1.3`.
 - Replace `/var/run/httpd.pid` with `/var/run/httpd-1.3.pid`.
- 10 Save your changes.
- 11 To migrate the web settings, in Terminal, run the following command:

```
sudo /System/Library/ServerSetup/translateApache.rb
```
- 12 If you've modified /etc/httpd/workers.properties, reapply all your changes to the version of the file that's installed with server v10.6.

The v10.6 workers.properties file has a new entry for Blog service.
- 13 In Server Admin, start Web service.

Web Content

Copy saved web content to the following locations and anywhere else you have placed web content on the server:

- /Library/WebServer/Documents/
- /Library/WebServer/CGI-Executables/

MySQL Data

Before importing backed up MySQL data, make sure that the MySQL service is active. You can activate the MySQL service using Server Admin or the `serveradmin` command.

To activate the MySQL service using the `serveradmin` command, enter:

```
serveradmin start mysql
```

To import database backups enter:

```
mysql < backup-file.sql
```

To import data into databases that require privileged access, run `mysql` with the `--user=root` and `-p` options:

```
mysql --user=root -p < backup-file.sql
```

The `-p` option causes `mysql` to prompt for the MySQL root password before proceeding.

When running MySQL and PHP on the same server, you may find that PHP cannot connect to MySQL or that authentication errors occur when using PHP. For more information and workarounds, see the following AppleCare KnowledgeBase articles:

- “Mac OS X Server 10.4: PHP and MySQL authentication issues” (article 301456)”
- “Mac OS X Server 10.4: Issues connecting PHP to MySQL” (article 301457)”

Additional instructions for MySQL database backup and restoration can be found in the MySQL documentation at www.mysql.org.

Mail Database

To migrate the mail database:

- 1 Make sure that v10.6 Mail server isn't running.

Open Server Admin, then click Mail. If the Mail circle on the left side is not grayed out, click Stop Mail at the lower left.

- 2 Restore the saved mail database and mail store.

By default the mail database resides in `/var/imap/` and the mail store in `/var/spool/imap/`.

- 3 Make sure the mail directories and their contents are owned by the `_cyrus` user and mail group.

- 4 In Server Admin, select Mail from the list of computers and services.

- 5 Click Settings, click Advanced, and click Database to indicate where you restored the database and mail store.

- 6 Click Save.

- 7 Run the mail database `61_migrate_cyrus_db` script:

```
sudo /System/Library/ServerSetup/MigrationExtras/61_migrate_cyrus_db
```

- 8 Run the following command to ensure that the index files for all mail accounts are in good working order:

```
sudo /usr/bin/cyrus/bin/reconstruct -i
```

- 9 In Server Admin, start Mail server by clicking Mail, then click Start Mail.

Webmail Data

Place saved address books and preferences in `/var/db/squirrelmail/data/`.

FTP Configuration Files

Copy saved FTP configuration files to:

- `/Library/FTPServer/Configuration/`
- `/Library/FTPServer/Messages/`

LDAP Server Settings

Restore the LDAP server configuration information.

To restore the Open Directory database, which includes LDAP server configuration:

- 1 In Server Admin, select Open Directory from the list of computers and services:
- 2 Click Archive.
- 3 In the “Archive from” field, browse for the archive.
- 4 Click the Restore button.
- 5 In the Password field, enter the password for the archive.
- 6 Click OK.

AFP Configuration

To migrate the AFP configuration, restore `/Library/Preferences/com.apple.AppleFileServer.plist`.

SMB Configuration

To migrate the SMB configuration, copy `/etc/smb.conf.old` to the new server, and run the following script:

```
sudo /System/Library/ServerSetup/MigrationExtras/70_smbconfigmigrator
```

This script generates the settings in `/Library/Preferences/SystemConfiguration/com.apple.smb.server.plist` for the v10.6 server using the settings from `/etc/smb.conf.old`.

NetBoot Images

Copy the `<name>.nbi` folder for each image you want to migrate, optionally placing it into the location where it previously resided.

Also, restore the NetBoot settings file.

To restore the NetBoot settings:

- 1 Open Server Admin and select NetBoot from the list of computers and services.
- 2 Choose Server > Import > Service Settings to import the NetBoot settings from the file you exported earlier (see “NetBoot Images” on page 62).
- 3 Review the NetBoot settings to make sure they were imported correctly.

Tomcat Data

Restore Tomcat servlets to `/Library/Tomcat/webapps/`.

Place SOAP services you want to migrate in `/Library/Tomcat/webapps/axis/`.

Mac OS X Server v10.6 includes a version of Axis that may be newer or older than the version you've been using.

JBoss Applications

JBoss does not come with Mac OS X Server v10.6. Before you can restore your JBoss applications, install JBoss on your server.

For more information about installing and migrating JBoss applications, see the JBoss documentation.

IP Firewall Configuration

To migrate the IP firewall configuration, restore the `/etc/ipfilter` folder.

Open Server Admin and click Firewall to inspect the settings and make sure they are correct.

NAT

Restore the contents of `/etc/nat/natd.plist`.

You can restore the v10.6 default settings for NAT (stored in `/etc/natd/natd.plist.default`) at any time by deleting the active configuration file (`/etc/nat/natd.plist`). The next time NAT is accessed using Server Admin, the default configuration file is used to recreate the active configuration file.

Note: In v10.6, the default setting of `unregistered_only` in `/etc/nat/natd.plist.default` is true.

Print Server Settings

To restore Print server settings, you must first recreate the original CUPS queues before importing the saved settings.

In the case of printers connected directly to the server via USB, the queues are created by CUPS when the printers are plugged in and turned on. However, for network printers, you must add the printers using Server Admin > Print (for LPR or AppleTalk printers) or System Preferences > Print & Fax (for all printer types).

Important: When recreating a CUPS queue, make sure you give it the same name as the one it had on the older system. If the name is not the same, Server Admin won't import the settings correctly.

Important: When creating the print queues using the Print & Fax pane of System Preferences, specify Generic Postscript (Generic PPD) for any queue that enforces quotas because there are known issues with third-party printer drivers and CUPS quotas. For more information about this issue, see the Knowledge Base article at <http://docs.info.apple.com/article.html?artnum=303538>.

After creating the print queues, import the saved settings:

```
serveradmin settings exported_print_settings
```

VPN

Restore the following:

- /Library/Preferences/SystemConfiguration/com.apple.RemoteAccessServers.plist.
 - /Library/Keychains/System.keychain
 - /etc/racoon/psk.text
- If L2TP is set up and psk.text stores the IPsec shared secret, the shared secret may also be stored in com.apple.RemoteAccessServers.plist or System.keychain.

Migrate the VPN MPPE Key user by using the `vpnaddkeyagentuser` command-line tool. For more information about this command, see its man page.

DNS Configuration

To migrate the DNS configuration:

- 1 Restore the file /etc/named.conf and the directory /var/named/ and all its contents.
- 2 In Server Admin, select DNS from the list of computers and services.

A dialog box appears prompting you whether to upgrade:

- If you click Don't Upgrade, Server Admin leaves the DNS configuration files as they were before the v10.6 migration. DNS will still run, but you can't make DNS configuration changes using Server Admin. To make changes, you must directly edit the DNS configuration files.
- If you click Upgrade, Server Admin upgrades the configuration files to the v10.6 format. After that, you can use Server Admin to make DNS configuration changes.

DHCP Settings

To migrate the DHCP configuration:

- 1 Open Server Admin and select DHCP from the list of computers and services.
- 2 Choose Server > Import > Service Settings to import DHCP settings from the file you exported earlier (see "DHCP" on page 63).
- 3 Inspect the Subnets and Static Maps panes of the DHCP service to make sure the subnet and static binding settings have been imported correctly.

User Data

Restore saved user data files.

Place home directories in locations that match the locations in the imported user records. If necessary, you can use Workgroup Manager to edit user accounts so the locations in the account and on disk are the same.

QuickTime Streaming Server Files and Folders

Follow instructions in *QuickTime Streaming and Broadcasting Administration* to reuse files and folders saved from `/Library/QuickTimeStreaming/`.

QTSS Publisher Files and Folders

QTSS Publisher has been removed from Mac OS X Server v10.6. However, files created using the QTSS Publisher on v10.4 should continue to work on v10.6.

Restore QTSS Publisher files and folders on Mac OS X Server v10.6.

QTSS Publisher Media and MP3 files should be stored in:

- `/Library/Application Support/Apple/QTSS Publisher/Libraries/`
- `/Users/<publisher_user>/Library/Application Support/Apple/QTSS Publisher/Libraries/`

To migrate QTSS Publisher media and MP3 playlists to QTSS Web Admin:

- 1 Move all folders in `/Library/Application Support/Apple/QTSS Publisher/Playlists/` to `/Library/QuickTimeStreaming/Playlists/`.

For example, you would move:

`/Library/Application Support/Apple/QTSS Publisher/Playlists/my_playlist/`

to

`/Library/QuickTimeStreaming/Playlists/my_playlist/`

- 2 Verify that the owner of folders and files in `/Library/QuickTimeStreaming/Playlists` is `qtss`.
- 3 For media playlists, verify that the folder `/Library/Application Support/Apple/QTSS Publisher/Libraries/Media/` contains the media files listed in the `.playlist` files.
- 4 For MP3 playlists, verify that the folder `/Library/Application Support/Apple/QTSS Publisher/Libraries/MP3/` contains the media files listed in the `.playlist` files.
- 5 For every playlist, update its `.config` file so that paths point to the new playlist folder in `/Library/QuickTimeStreaming/Playlists`.

This includes the paths defined in the `pid_file`, `playlist_file`, and `sdp_file` (media playlists only) preferences.

- 6 Enable QTSS web-based administration using Server Admin.
- 7 Open Web Admin using Safari (`http://<hostname>:1220`) and log in.
- 8 Click Playlists.

You can now start manage QTSS Publisher playlists using QTSS Web Admin.

For information about using Web Admin, see the *QuickTime Streaming Server Darwin Streaming Server Administrator's Guide* available at developer.apple.com/opensource/server/streaming.

iChat Server

To migrate iChat server settings:

- 1 Restore the following folders:

- /var/jabber/spool
- /etc/jabber

- 2 Run the following script with root privileges:

```
sudo "/System/Library/ServerSetup/MigrationExtras/  
58_jabbermigrator.pl
```

The `58_jabbermigrator.pl` script invokes three other scripts to migrate the iChat server settings. If needed, you can run these scripts individually to customize the migration. The scripts are documented and contain helpful information.

Step 8: Set up share points and privileges

Recreate the share points and privileges as required.

To create a share point and set privileges:

- 1 Open Server Admin and click File Sharing.
- 2 Click Volumes and select the volume or folder you want to share.
- 3 Click Share.
- 4 Click Permissions to set up access privileges.
- 5 Click Save.

New share points are shared using AFP, SMB, and FTP, but not NFS. To export a share point using NFS, use the Protocol pane. For more information about setting up share points, see *File Server Administration*.

Step 9: Test the new server

To test the new server:

- 1 Open Workgroup Manager and inspect user and group accounts.
- 2 Open Server Admin and inspect settings for services whose configuration data you migrated.

Index

A

- access
 - ACLs 21, 52
 - See also* LDAP; permissions; SOAP
- accounts. *See* Workgroup Manager; users; groups
- ACLs (access control lists) 21, 52
- admin group 12
- administrator, privileges of 12
- AFP (Apple Filing Protocol) service
 - v10.4 migration 32, 39, 62, 69
- Apache server
 - v10.4 upgrade 15, 22, 45, 53
- Apple Filing Protocol service. *See* AFP
- archiving
 - v10.4 migration 29, 34, 59, 64
- authentication 21, 51
 - See also* Kerberos; passwords

B

- basic authentication. *See* crypt passwords

C

- Certificate Signing Request. *See* CSR
- certificates, importing 20, 51
- chat service. *See* iChat
- CIFS (Common Internet File System). *See* SMB/CIFS
- clients. *See* users; groups
- command-line tools
 - archiving 29, 59
 - copying 29, 59
 - home folders 36, 66
 - importing 11, 26, 56
 - login 11
 - remote file copying 29, 59
 - substitute user 11
- Common UNIX Printing System. *See* CUPS
- configuration
 - v10.4 upgrade 17, 18, 48
- createhomedir tool 36, 66
- crypt passwords 21, 36, 51, 66
- CSR (Certificate Signing Request) 20, 51
- CUPS (Common UNIX Printing System)
 - v10.4 migration 33, 40, 63, 70

- v10.4 upgrade 17, 19, 47, 50

D

- DHCP (Dynamic Host Configuration Protocol)
 - service
 - v10.4 migration 24, 33, 41, 54, 63, 71
 - v10.4 upgrade 16, 46
- directories. *See* home folders; directory services
- directory services and upgrading 51
 - See also* Open Directory
- disk images, archiving files 29, 59
 - See also* NetBoot service
- DNS (Domain Name System) service
 - v10.4 migration 33, 41, 63, 71
 - v10.4 upgrade 21, 52
- documentation 6, 7, 8
- Domain Name System. *See* DNS
- domains, directory. *See* Open Directory
- dsimport tool 11, 26, 56
- Dynamic Host Configuration Protocol. *See* DHCP

E

- email. *See* mail service
- exporting
 - server settings 17, 47
 - users and groups 26, 28, 56, 58
 - See also* importing

F

- file sharing
 - v10.4 migration 35, 65
 - See also* share points
- File Transfer Protocol. *See* FTP
- files
 - relocation of 36, 67
 - See also* archiving
- firewall service
 - v10.4 migration 33, 40, 63, 70
- folders. *See* home folders
- FTP (File Transfer Protocol) service
 - v10.4 migration 31, 39, 61, 69

G

Generic Postscript (Generic PPD) 20, 50
group accounts, saving and reusing 11
groups
 exporting 26, 28, 56, 58
 importing 35, 65
 predefined accounts 11, 12
 upgrading 21, 51

H

help, using 6
home folders
 v10.4 migration 34, 36, 64, 66
hosts. *See* servers

I

iChat service 34, 42, 64, 73
images. *See* NetBoot service; disk images
importing
 dsimport tool 11, 26, 56
 groups 35, 65
 SSL certificates 20, 51
 users 35, 65
 See also exporting
installation, upgrade 17, 47
IP firewall service. *See* firewall service

J

JBoss applications
 v10.4 migration 63, 70
jobs, print (queues) 20, 50

K

Kerberos
 v10.4 migration 36, 66
 v10.4 upgrade 21, 51

L

LDAP (Lightweight Directory Access Protocol)
 service
 v10.4 migration 32, 39, 62, 69
 v10.4 upgrade 21, 51, 52
Leopard server. *See* Mac OS X Server
Lightweight Directory Access Protocol. *See* LDAP
login
 root user 11
logs, Open Directory 22, 52

M

Mac OS X Server
 See also under version
mail service
 v10.4 migration 31, 38, 61, 68
 See also webmail
migration vs. upgrading 5, 10, 11

MySQL

v10.4 migration 30, 37, 60, 67

N

NAT (Network Address Translation)
 v10.4 migration 33, 40, 63, 70
NetBoot service
 v10.4 migration 32, 39, 62, 69
 v10.4 upgrade 15, 22, 45, 52
Network Address Translation. *See* NAT
network services. *See* VPN; NAT; IP addresses; firewall
 service; DNS; DHCP

O

Open Directory
 logs 22, 52
 v10.4 migration 24, 32, 39, 54, 62, 69
 v10.4 upgrade 16, 22, 46, 52
Open Directory master
 v10.4 migration 24, 54
 v10.4 upgrade 16, 46
Open Directory replica
 v10.4 migration 24, 54
 v10.4 upgrade 16, 46
OpenLDAP
 See also Open Directory

P

passwords
 crypt 21, 36, 51, 66
 Open Directory 21, 51
 root user login 11
 v10.4 migration 29, 35, 36, 59, 66
 v10.4 upgrade 21, 51
permissions
 administrator 12
 root 11
 v10.4 migration 34, 43, 64, 73
PHP Hypertext Preprocessor (PHP) 15, 45
predefined accounts 11, 12
print service
 v10.4 migration 33, 40, 63, 70
 v10.4 upgrade 17, 19, 47, 50
private network. *See* VPN
privileges, administrator 12
 See also permissions

Q

QTSS Publisher
 v10.4 migration 34, 41, 64, 72
 v10.4 upgrade 45
queues, print 20, 50
QuickTime Streaming Server (QTSS)
 v10.4 migration 34, 41, 64, 72

R

remote servers, upgrading 18, 48
requirements, system 10, 24, 54
root permissions 11
rsync tool 29, 59

S

scp tool 29, 59
Secure Sockets Layer. *See* SSL
security
 authentication 21, 51
 SSL certificates 20, 51
 See also access; firewall service; Kerberos;
 passwords
serial number, server 14
Server Admin 26, 56
Server Message Block/Common Internet File System.
 See SMB/CIFS
servers
 remote upgrades 18, 48
 serial number 14
 testing 43, 73
 See also under version
setup procedures. *See* installation; configuration
share points
 v10.4 migration 34, 43, 64, 73
shared files. *See* file sharing
Simple Object Access Protocol. *See* SOAP
SMB/CIFS (Server Message Block/Common Internet
 File System) protocol service
 v10.4 migration 32, 39, 62, 69
SOAP (Simple Object Access Protocol)
 v10.4 migration 33, 40, 63, 70
Software Update service 17, 47
ssh tool 12
SSL (Secure Sockets Layer) certificates 20, 51
su tool 12
system accounts 11

T

tar tool 29, 59
Tomcat Application Server
 v10.4 migration 33, 39, 63, 70

U

updating software 17, 47
upgrading vs. migration 5, 10, 11
user accounts 11
 See also users
users
 exporting 26, 28, 56, 58
 importing 35, 65
 login 11
 root 11
 v10.4 migration 34, 41, 64, 71

See also groups; home folders; user accounts

V

version 10.2 migration 10
version 10.3
 migration 10
 upgrade 10
version 10.4
 migration 10, 24, 25, 26, 28, 54, 55, 56, 58
 upgrade 10, 15, 16, 22, 45, 46, 47, 53
VPN (Virtual Private Network)
 v10.4 migration 33, 40, 63, 71

W

web service
 v10.4 migration 30, 37, 60, 67
 v10.4 upgrade 22, 52
webmail
 v10.4 migration 31, 38, 61, 69
wheel group 11
Windows domain. *See* SMB/CIFS
Windows NT migration
 overview 10
Workgroup Manager
 exporting users and groups 26, 28, 56, 58
 importing users and groups 35, 65
 password upgrading 21, 51
 saving and reusing users and groups 11

X

Xserve, remote upgrade installation with 18, 48